

- 2 Document Number: DSP1053 3 Date: 2009-12-11
- 4 Version: 1.0.1

5 Base Metrics Profile

- 6 Document Type: Specification
- 7 Document Status: DMTF Standard
- 8 Document Language: E
- 9

1

10 Copyright notice

11 Copyright © 2009 Distributed Management Task Force, Inc. (DMTF). All rights reserved.

DMTF is a not-for-profit association of industry members dedicated to promoting enterprise and systems
 management and interoperability. Members and non-members may reproduce DMTF specifications and
 documents, provided that correct attribution is given. As DMTF specifications may be revised from time to

15 time, the particular version and release date should always be noted.

16 Implementation of certain elements of this standard or proposed standard may be subject to third party

17 patent rights, including provisional patent rights (herein "patent rights"). DMTF makes no representations

to users of the standard as to the existence of such rights, and is not responsible to recognize, disclose,

or identify any or all such third party patent right, owners or claimants, nor for any incomplete or inaccurate identification or disclosure of such rights, owners or claimants. DMTF shall have no liability to

any party, in any manner or circumstance, under any legal theory whatsoever, for failure to recognize,

disclose, or identify any such third party patent rights, or for such party's reliance on the standard or

incorporation thereof in its product, protocols or testing procedures. DMTF shall have no liability to any

party implementing such standard, whether such implementation is foreseeable or not, nor to any patent

25 owner or claimant, and shall have no liability or responsibility for costs or losses incurred if a standard is

withdrawn or modified after publication, and shall be indemnified and held harmless by any party

implementing the standard from any and all claims of infringement by a patent owner for such

28 implementations.

29 For information about patents held by third-parties which have notified the DMTF that, in their opinion,

- 30 such patent may relate to or impact implementations of DMTF standards, visit
- 31 <u>http://www.dmtf.org/about/policies/disclosures.php</u>.

CONTENTS

33	Fore	eword.		7
34	Intro	oductio	n	8
35	1)	
36	2	•	ative References	
37	3		s and Definitions	
38	4	-	ols and Abbreviated Terms	
39	5		osis	
40	6		iption (Informative)	
41		6.1	Metric Access Types	
42		6.2	Metric Time Scope	
43		6.3	Metric Value Formulation	
44		6.4	Metric Context	
45	7	Imple	mentation	
46		7.1	Common Requirements	
47		7.2	Modeling Metric Access Types	
48		7.3	Modeling Metric Time Scope	
49		7.4	Modeling Metric Value Formulation	
50		7.5	Relationship between Aggregation and Base Metrics	
51		7.6	Constraints on Metric Values for Controllable Metrics	. 19
52	8	Metho	ods	
53		8.1	CIM_MetricService.ShowMetrics()	20
54		8.2	CIM_MetricService.ShowMetricsByClass()	21
55		8.3	CIM_MetricService.ControlMetrics()	22
56		8.4	CIM_MetricService.ControlMetricsByClass()	24
57		8.5	CIM_MetricService.GetMetricValues()	25
58		8.6	Profile Conventions for Operations	25
59		8.7	CIM_AggregationMetricDefinition	
60		8.8	CIM_AggregationMetricValue	
61		8.9	CIM_BaseMetricDefinition	
62		8.10	CIM_BaseMetricValue	. 26
63		8.11	CIM_ConcreteDependency	
64		8.12	CIM_ElementCapabilities	
65		8.13	CIM_HostedService	
66		8.14	CIM_MetricDefForME	
67		8.15	CIM_MetricForME	
68		8.16	CIM_MetricInstance	
69		8.17	CIM_MetricService	
70		8.18	CIM_MetricServiceCapabilities	
71		8.19	CIM_ServiceAffectsElement	
72	9	Use C	Cases (Informative)	
73		9.1	Instructions Executed per Second	
74		9.2	Object Diagram for Startup Interval Time Scope	. 33
75		9.3	Metric Definition for Multiple Instances of CIM_ManagedElement	
76		9.4	Controllable Metrics	. 35
77		9.5	Aggregation Metrics	. 41
78		9.6	Metric Context	
79		9.7	Find All Metric Definitions for a Managed Element	
80		9.8	Find the Metric Value for a Managed Element	
81		9.9	Find a Standard Metric for a Managed Element	
82		9.10	Retrieve a Metric Value.	
83		9.11	Find All Metrics Available for a Managed Element within an Enumeration Scope	45

84 85 86		9.12 9.13	Find All Metrics Available within an Enumeration Scope for All Instances of a CIM Class Determine whether a Metric Can Be Discretely Controlled for a Specific Managed Element	. 46
87		9.14	Enable a Specific Metric for a Specific Managed Element	. 46
88		9.15	Find All Managed Elements within an Enumeration Scope for which a Metric Is Currently	
89			Being Collected	
90	10			
91		10.1	CIM_AggregationMetricDefinition	
92		10.2	CIM_AggregationMetricDefinition (Low Watermark)	
93 94		10.3 10.4	CIM_AggregationMetricDefinition (High Watermark) CIM_AggregationMetricValue	
94 95		10.4	CIM_AggregationMetricValue	
96		10.5	CIM_BaseMetricDefinition — Instantaneous Metric	
97		10.7	CIM BaseMetricDefinition — Interval Metric	
98		10.8	CIM_BaseMetricDefinition — Startup Interval Metric	
99		10.9		
100		10.10	CIM_BaseMetricDefinition — Current Data	
101			CIM_BaseMetricValue	
102			CIM_BaseMetricValue — Current Data	
103			CIM_BaseMetricValue — Interval Metrics	
104			CIM_BaseMetricValue — Startup Interval Metrics	
105			CIM_BaseMetricValue — Summation Metric	
106 107			CIM_BaseMetricValue — Long-Term Monitoring	
107			CIM_ConcreteDependency (Definition)	
109			CIM_ElementCapabilities	
110			CIM HostedService	
111			CIM MetricDefForME	
112			CIM_MetricForME	
113		10.23	CIM_MetricInstance	. 54
114			CIM_MetricService	
115			CIM_MetricServiceCapabilities	
116			CIM_RegisteredProfile	
117			CIM_ServiceAffectsElement	
118			(Informative) Change Log	
119			(Informative) Guide for Common Metrics	
120	Bibli	ograpl	hy	.71
121				
122	Figu	ures		
123	Figu	re 1 –	Base Metrics Profile: Class Diagram	13
124	-		Interval Metrics	
125	•		Instantaneous Counter	
126	-		Instantaneous Gouge	
120	-		Usage Example for Startup Interval Time Scope	
	-			
128	-		Common Metric Definition for Multiple Instances of CIM_ManagedElement	
129	•		Advertising Support for Discrete Controllable Metrics	
130	-		Discrete Controllable Metrics (Before Enable)	
131	-		Discrete Controllable Metrics (After Enable)	
132	-		 Bulk Controllable Metrics by Definition 	
133	-		 Bulk Controllable Metrics by Managed Element 	
134	Figu	re 12 ·	Bulk Controllable Metrics by Class	. 40
135	Figu	re 13 ·	- Aggregation Metric without Base	. 41

136 137 138	Figure 14 – Aggregation Metric with Base Figure 15 – Metric Context	
139	Tables	
140	Table 1 – Referenced Profiles	. 12
141	Table 2 – CIM_MetricService.ShowMetrics() Method: Return Code Values	. 20
142	Table 3 – CIM_MetricService.ShowMetrics() Method: Parameters	. 21
143	Table 4 – CIM_MetricService.ShowMetricsByClass() Method: Return Code Values	. 21
144	Table 5 – CIM_MetricService.ShowMetricsByClass() Method: Parameters	. 22
145	Table 6 – CIM_MetricService.ControlMetrics() Method: Return Code Values	. 22
146	Table 7 – CIM_MetricService.ControlMetrics() Method: Parameters	. 23
147	Table 8 - CIM_MetricService.ControlMetricsByClass() Method: Return Code Values	. 24
148	Table 9 - CIM_MetricService.ControlMetricsByClass() Method: Parameters	. 24
149	Table 10 - CIM_MetricService.GetMetricValues() Method: Return Code Values	. 25
150	Table 11 – CIM_MetricService.GetMetricValues() Method: Parameters	. 25
151	Table 12 – Operations: CIM_ConcreteDependency	. 26
152	Table 13 – Operations: CIM_ElementCapabilities	. 27
153	Table 14 – Operations: CIM_HostedService	. 27
154	Table 15 – Operations: CIM_MetricDefForME	. 27
155	Table 16 – Operations: CIM_MetricForME	. 28
156	Table 17 – Operations: CIM_MetricInstance	. 28
157	Table 18 – Operations: CIM_ServiceAffectsElement	. 29
158	Table 19 – CIM Elements: Base Metrics Profile	. 47
159	Table 20 – Class: CIM_AggregationMetricDefinition	. 48
160	Table 21 – Class: CIM_AggregationMetricDefinition (Low Watermark)	. 48
161	Table 22 – Class: CIM_AggregationMetricDefinition (High Watermark)	. 48
162	Table 23 – Class: CIM_AggregationMetricValue	. 49
163	Table 24 – Class: CIM_BaseMetricDefinition	. 49
164	Table 25 – Class: CIM_BaseMetricDefinition – Instantaneous Metric	. 50
165	Table 26 – Class: CIM_BaseMetricDefinition – Interval Metric	. 50
166	Table 27 – Class: CIM_BaseMetricDefinition – Startup Interval Metric	. 50
167	Table 28 – Class: CIM_BaseMetricDefinition – Summation Metric	. 50
168	Table 29 – Class: CIM_BaseMetricDefinition – Current Data	. 51
169	Table 30 – Class: CIM_BaseMetricValue	. 51
170	Table 31 – Class: CIM_BaseMetricValue – Current Data	. 51
171	Table 32 – Class: CIM_BaseMetricValue – Interval Metrics	. 52
172	Table 33 – Class: CIM_BaseMetricValue – Startup Interval Metrics	. 52
173	Table 34 – Class: CIM_BaseMetricValue – Summation Metric	. 52
174	Table 35 – Class: CIM_BaseMetricValue – Long-Term Monitoring	. 52
175	Table 36 – Class: CIM_ConcreteDependency (Definition)	. 53
176	Table 37 – Class: CIM_ConcreteDependency (Value)	. 53
177	Table 38 – Class: CIM_ElementCapabilities	. 53
178	Table 39 – Class: CIM_HostedService	. 54
179	Table 40 – Class: CIM_MetricDefForME	. 54
180	Table 41 – Class: CIM_MetricForME	. 54
181	Table 42 – Class: CIM_MetricInstance	. 54
182	Table 43 – Class: CIM_MetricService	. 55

183	Table 44 – Class: CIM_MetricServiceCapabilities	55
184	Table 45 – Class: CIM_RegisteredProfile	
185	Table 46 – Class: CIM_ServiceAffectsElement	
186	Table B.1 – Simple Metric	59
187	Table B.2 – Summation Metric	61
188	Table B.3 – Aggregation Metric	63
189	Table B.4 – Aggregation Metric – Low Watermark	65
190	Table B.5 – Aggregation Metric – High Watermark	68
191		

Foreword

- 193 The Base Metrics Profile (DSP1053) was prepared by the Applications Working Group of the DMTF.
- 194 DMTF is a not-for-profit association of industry members dedicated to promoting enterprise and systems 195 management and interoperability.

196 Acknowledgments

- 197 The authors wish to acknowledge the following people.
- 198 Editors:
- 199 Oliver Benke IBM
- Aaron Merkin IBM
- Khachatur Papanyan Dell

202 Contributors:

- 203 Andreas Maier --- IBM
- Karl Schopmeyer The Open Group

Introduction

The information in this specification should be sufficient for a provider or consumer of this data to identify unambiguously the classes, properties, methods, and values that shall be instantiated and manipulated to represent and manage the components described in this document.

209 The target audience for this specification is implementers who are writing Common Information Model

(CIM)-based providers or consumers of management interfaces that need to dynamically add metrics to
 existing components.

Base Metrics Profile

212

213 **1 Scope**

- 214 The Base Metrics Profile is a component profile that defines the minimum object model needed to provide
- dynamic metrics associated to existing managed elements and related associations. This profile does not
- document how to model metrics for capacity planning or accounting purposes. These topics are covered
- 217 by the Capacity Metrics Profile (<u>DSP1073</u>), which is a specialization of this profile.

218 **2 Normative References**

- 219 The following referenced documents are indispensable for the application of this document. For dated
- references, only the edition cited applies. For undated references, the latest edition of the referenced
- 221 document (including any amendments) applies.
- 222 DMTF DSP0004, CIM Infrastructure Specification 2.3,
- 223 <u>http://www.dmtf.org/standards/published_documents/DSP0004_2.3.pdf</u>
- DMTF DSP0200, CIM Operations over HTTP 1.2,
 <u>http://www.dmtf.org/standards/published_documents/DSP0200_1.2.pdf</u>
- 226 DMTF DSP1001, *Management Profile Specification Usage Guide 1.0*, 227 <u>http://www.dmtf.org/standards/published_documents/DSP1001_1.0.pdf</u>
- DMTF DSP1033, Profile Registration Profile 1.0,
 <u>http://www.dmtf.org/standards/published_documents/DSP1033_1.0.pdf</u>
- 230 ISO/IEC Directives, Part 2, Rules for the structure and drafting of International Standards,
- 231 http://isotc.iso.org/livelink/livelink.exe?func=ll&objld=4230456&objAction=browse&sort=subtype

3 Terms and Definitions

- 233 For the purposes of this document, the following terms and definitions apply.
- 234 **3.1**
- 235 **can**
- used for statements of possibility and capability, whether material, physical, or causal
- 237 **3.2**
- 238 cannot
- used for statements of possibility and capability, whether material, physical, or causal
- 240 **3.3**
- 241 conditional
- indicates requirements to be followed strictly in order to conform to the document when the specified
- 243 conditions are met

DSP1053

244	3.4
245	mandatory
246	indicates requirements to be followed strictly in order to conform to the document and from which no
247	deviation is permitted
248	3.5
249	may
250	indicates a course of action permissible within the limits of the document
251	3.6
252	need not
253	indicates a course of action permissible within the limits of the document
254 255 256	3.7optionalindicates a course of action permissible within the limits of the document
257	3.8
258	referencing profile
259	indicates a profile that owns the definition of this class and can include a reference to this profile in its
260	"Referenced Profiles" table
261 262 263 264	 3.9 shall indicates requirements to be followed strictly in order to conform to the document and from which no deviation is permitted
265	3.10
266	shall not
267	indicates requirements to be followed in order to conform to the document and from which no deviation is
268	permitted
269	3.11
270	should
271	indicates that among several possibilities, one is recommended as particularly suitable, without
272	mentioning or excluding others, or that a certain course of action is preferred but not necessarily required
273	3.12
274	should not
275	indicates that a certain possibility or course of action is deprecated but not prohibited
276	3.13
277	unspecified
278	indicates that this profile does not define any constraints for the referenced CIM element or operation
279	3.14
280	aggregation metric
281	a type of metric that is derived by applying a formula or filter to a set of base metric values
282	3.15
283	base metric
284	a metric provided directly without a dependency on other metric values

285 **3.16**

286 measured resource

- a managed object being measured, which is the resource to which base metric value instances are
 associated
- 289 **3.17**

290 sampling interval

- a value that determines how often new metric values are retrieved, if metrics are retrieved periodically
- 292 **3.18**

293 current data

the most current data available for a given metric. Online monitoring (3.19) and snapshot monitoring (3.20) are types of current data access.

296 **3.19**

297 online monitoring

- the process in which metric values (typically interval metrics) are gathered asynchronously to a request
- 299 from the instrumentation or reporting layer

300 **3.20**

301 snapshot monitoring

- 302 the process in which metric values are gathered synchronously with a request from the instrumentation or 303 reporting layer
- 304 **3.21**

305 long-term monitoring

- 306 the process in which metric values are captured during an interval
- 307 **3.22**

308 event-based monitoring

- 309 the process in which threshold values for metrics are used to trigger asynchronous notification
- 310 3.23

311 instantaneous metrics

312 metrics that apply to a particular point in time. An example of an instantaneous metric is the amount of 313 memory currently allocated to a virtual server.

314 **3.24**

315 interval metrics

- metrics that apply to a time interval. An example of an interval metric is the average CPU utilization of a
 server over the past hour.
- 318 3.25

319 summation metrics

- 320 a type of counter metric that reflects the accumulation of a value
- 321 **3.26**

322 watermark metrics

- a type of aggregation metric used to capture the minimum or maximum value recorded for a monitored
- 324 value

325 **4 Symbols and Abbreviated Terms**

326 327 328	4.1 CPU central processing unit
329 330 331	4.2 IEPS instructions executed per second
332 333 334	4.3 UTC Universal Time Coordinated
335 336 337	4.4 UUID Universally Unique Identifier
338	5 Synopsis
339	Profile Name: Base Metrics
340	Version: 1.0.1
341	Organization: DMTF
342	CIM Schema Version: 2.23
343	Central Class: CIM_MetricService
344	Scoping Class: CIM_System
345	Table 1 identifies profiles on which this profile has a dependency.

346

Table 1 – Referenced Profiles

Profile Name	Organization	Version	Relationship	Behavior
Profile Registration	DMTF	1.0	Mandatory	

347 6 Description (Informative)

348 The Metrics Model provides the ability to model and control metrics captured for managed elements.

Figure 1 represents the class schema for the *Base Metrics Profile*. For simplicity, the prefix CIM_ has been removed from the names of the classes.



352

Figure 1 – Base Metrics Profile: Class Diagram

353 A metric instance is represented by an instance of CIM_BaseMetricValue or its subclass

354 CIM_AggregationMetricValue. The definition of the metric is provided by an associated instance of

355 CIM_BaseMetricDefinition or CIM_AggregationMetricDefinition. The context of the metric is provided by

one or more associated instances of CIM_ManagedElement. For example, an instance of

357 CIM_ManagedElement could represent an operating system, a cluster, or a complex software application 358 containing application server and database server parts. The modeling of the associated resources is out

359 of the scope of this profile.

360 When defining a metric, there are four main characteristics to consider:

- Metric access type
- Time scope of the metric
- Formulation of the metric value
- Metric context

These characteristics are described in the following sections. Some of these characteristics are modeled as attributes of an instance of CIM_BaseMetricDefinition. Others are modeled through the relationship of an instance of CIM_BaseMetricDefinition or CIM_BaseMetricValue to one or more instances of CIM_ManagedElement.

369 6.1 Metric Access Types

- 370 There are three major access types for metrics and performance data:
- Current data access, for data gathered in the recent past
- Long-term monitoring, for historical time series data
- Event-based monitoring, for asynchronous indication subscriptions based on instances of CIM_BaseMetricValue

375 6.1.1 Current Data

376 Current data access is the most common access type for dynamic metrics. The purpose is to request the

377 most current data available to the implementation. There are two paradigms for the gathering metrics with 378 an access type of current data, online monitoring and snapshot monitoring. For the current data access type, CIM_BaseMetricValue.Volatile is equal to TRUE. The metric value property is updated at the point in time that the instance is read.

381 6.1.1.1 Online Monitoring

For the online monitoring access type, the CIM metric values are updated independently by the gathering infrastructure. When a new metric value is requested, the most current value is presented. Typically, the implementation of the gathering and reporting components can be separated. It is recommended to synchronize metric retrieval in order to allow for correlation of various metrics. For the online monitoring access type, the value of the CIM_BaseMetricDefinition.GatheringType property is 3 (Periodic) or 2 (OnChange).

388 A well known UNIX application that implements this access type is "top".

389 6.1.1.2 Snapshot Monitoring

For the snapshot monitoring access type, the CIM metric value is determined each time a client
 application requests a new metric value. The value of the CIM_BaseMetricDefinition.GatheringType
 property is 4 (OnRequest).

Note that this access type has disadvantages. For example, data generated by snapshot monitoring is not always suitable for event correlation. However, for simple investigations of the current state of the system, snapshot monitoring is suitable, and it has the advantage that the gathering infrastructure needs to be active only on request rather than continuously.

397 A well known UNIX application that implements this access type is "ps".

398 6.1.2 Long-Term Monitoring

The long-term monitoring access type is used for historical time series. For example, it could be used to collect all metric values gathered between 9:00 A.M. and 5:00 P.M. with 15 minute intervals.

- For the long-term monitoring access type, the value of the CIM_BaseMetricValue.Volatile property is FALSE. The metric value is stored in a repository and can be retrieved by client applications later on.
- 403 A well known UNIX application that implements this access type is "sar/sadc".
- 404 Important aspects of the long-term monitoring access type are described in the *Capacity Metrics Profile* 405 (<u>DSP1073</u>).

406 6.1.3 Event-Based Monitoring

The event-based monitoring access type is used for asynchronous indication subscriptions based on
 base metric value instances, which allows the client to subscribe for certain threshold conditions. This
 may be implemented based on CIM_InstModification subscriptions for CIM_BaseMetricValue changes.

410 Details on how to use event-based monitoring with dynamic metrics are out of the scope of this 411 document.

412 6.2 Metric Time Scope

413 Many common types of metrics can be captured. Metrics may be quantified along two axes. The first axis

- is the time scope, and the second axis is the type of value formulation. Along the time scope axis, metrics
- can be described as instantaneous, interval, or startup interval. Types of values captured include
- 416 minimum, maximum, average, instantaneous, and aggregate values.

417 **6.2.1 Instantaneous Metrics**

418 Instantaneous metrics report a monitored value at a given instant. An example of an instantaneous metric

is the amount of power being consumed by a system at a given instant. All example of an instantaneous metrics, the value of the CIM BaseMetricDefinition.TimeScope property is 2 (Point).

421 6.2.2 Interval Metrics

Interval metrics are metrics captured over an interval in time. Interval metrics can report values such as
the average utilization of a resource over a period of time. An example of an iInterval metric is the
average power consumption of a server over the last three days. For interval metrics, the value of the

425 CIM_BaseMetricDefinition.TimeScope property is 3 (Interval).

426 6.2.3 Startup Interval Metrics

427 Startup interval metrics are metrics captured over an interval in time, for which the start of the interval is
428 tied to a lifecycle change (initialization or creation) of the managed element for which the value is
429 captured. An example of a startup interval metric is the total number of CPU cycles consumed for a
430 transaction that is recorded from the time the transaction begins.

431 **6.3 Metric Value Formulation**

A metric's value may be constructed in innumerable ways. Three common types of metrics are simple
 metrics, summation metrics, and aggregation metrics. These types are described in more detail in the
 following clauses.

435 6.3.1 Simple Metrics

Simple metrics report status recorded at some point in time without requiring a calculation or function to
be applied to produce the value. An example of a simple metric is an instantaneous reading of the power
being consumed by a server.

439 6.3.2 Summation Metrics

Summation metrics are used to report aggregate or total values for a monitored entity. Uses of summation
 metrics include billing, accounting, and capacity planning. An example of a summation metric is the total
 power consumed by a server for the last three days.

443 More information on using summation metrics is specified in <u>DSP1073</u>.

444 6.3.3 Aggregation Metrics

Aggregation metrics are metrics derived by applying a formula or filter to a set of base metric values. 445 446 Aggregation metrics that apply a formula to metric values of multiple types are out of scope of this profile. 447 The definition of an aggregation metric is provided by an instance of CIM_AggregationMetricDefinition. An 448 aggregation metric includes the definition of a base metric as well as the function used to create the 449 derived value. A server-side implementation may support the collection of an aggregation metric without supporting the collection of the base metric. If collection of the base metric is supported, a distinct 450 instance of CIM BaseMetricDefinition is used to define the base metric and distinct instances of 451 452 CIM BaseMetricValue are used to represent the metric value. The CIM BaseMetricDefinition instance may be associated to the CIM_AggregationMetricDefinition instance, and the CIM_BaseMetricValue 453 instance may be associated with the CIM AggregationMetricValue instance. 454

455 6.3.3.1 Watermark Metrics

456 Watermark metrics are a class of aggregation metrics. A watermark metric captures the highest or lowest

436 Watermark metrics are a class of aggregation metrics. A watermark metric captures the highest of lowest
 457 value recorded for a monitored entity. An example of a high watermark metric is the peak instantaneous
 458 power consumed by a server in the past hour.

459 6.4 Metric Context

Generally it is necessary to understand the context of a metric in order to properly interpret and utilize the reported values. An example is a metric that reports the number of packet errors per minute. If the metric is reported for a single network interface, a much lower value is a cause for concern than if the metric is for an entire network segment.

- The CIM_MetricForME and CIM_MetricDefForME associations are used to provide the context in which a metric is captured. CIM_MetricDefForME associates an instance of CIM_BaseMetricDefinition with an
- 466 instance of CIM_ManagedElement. This indicates that the metric defined by the
- 467 CIM_BaseMetricDefinition can be captured for the resource modeled with the instance of
- 468 CIM_ManagedElement. The same metric can be available for multiple instances of
- 469 CIM_ManagedElement simultaneously. Therefore, it is necessary to further disambiguate the specific
- 470 instance of CIM_ManagedElement for which a particular instance of the metric has been captured. The
- 471 CIM_MetricForME association is used to associate an instance of CIM_BaseMetricValue with the
- 472 instances of CIM_ManagedElement that provide its context.
- 473 A given defined metric may have multiple values available concurrently for a CIM_ManagedElement
- instance. The BreakdownValue and BreakdownDimension properties are used to differentiate among the
- instances of CIM_BaseMetricValue that provide multiple concurrent metric values for a
- 476 CIM_ManagedElement. An example of when multiple metric values for the same metric definition may be
- 477 available is when a total value and values per component exist.

478 **7** Implementation

This section details the requirements related to the arrangement of instances and their properties for implementations of this profile.

481 **7.1 Common Requirements**

482 This section details the common requirements for modeling metrics. The requirements stated in this

- 483 section for the CIM_BaseMetricDefinition and CIM_BaseMetricValue classes shall also apply to the
- 484 CIM_AggregationMetricDefinition and CIM_AggregationMetricValue subclasses, respectively.

485 7.1.1 Service and Capabilities

- 486 At least one instance of CIM_MetricService shall exist. Each instance of CIM_MetricService shall be 487 associated with exactly one instance of CIM_System through the CIM_HostedService association. Each
- 488 instance of CIM_MetricService shall be associated with exactly one instance of
- 489 CIM_MetricServiceCapabilities through the CIM_ElementCapabilities association. Each instance of
- 490 CIM_BaseMetricDefinition shall be associated with exactly one instance of CIM_MetricService through
- 491 the CIM_ServiceAffectsElement association.

492 **7.1.2** Relating a Metric Definition and Metric Value

- 493 Each instance of CIM_BaseMetricValue shall be associated with exactly one instance of
 494 CIM_BaseMetricDefinition through the CIM_MetricInstance association.
- Each instance of CIM_AggregationMetricValue shall be associated with exactly one instance of
- 496 CIM_AggregationMetricDefinition through the CIM_MetricInstance association.

497 **7.1.3 Identifying a Metric Definition**

- Incorporating profiles may specify metric definitions for metrics that are applicable to the managementdomain of the incorporating profile.
- 500 If the incorporating profile is a DMTF Management Profile, the CIM_BaseMetricDefinition.Name shall be 501 formatted as follows:
- 502 "DMTF:<unique identifier> "
- 503 If the incorporating profile is not a DMTF Management Profile, the CIM_BaseMetricDefinition.Name 504 property shall be formatted as follows:
- S05
 OrgID > : < LocalID >, where < OrgID > and < LocalID > are separated by a colon (:) and
 S06
 S07
 S07
 S08
 S08
 S07
 S08
 S08
 S09
 S01
 S01
 S02
 S03
 S03
 S04
 S06
 S07
 S07
 S08
 S08
 S08
 S09
 S09
 S01
 S01
 S02
 S03
 S03
 S04
 S04
 S05
 S05
 S06
 S06
 S07
 S07
 S08
 S08
 S09
 S09
 S01
 S01
 S01
 S02
 S02
 S03
 S03
 S04
 S04
 S05
 S04
 S06
 S06
 S07
 S06
 S07
 S07
 S08
 S08
 S08
 S09
 S08
 S09
 S01
 S01
 S01
 S02
 S02
 S03
 S03
 S04
 S04
 S04
 S04
 S06
 S06
 S07
 S06
 S07
 S07
 S07
 S08
 S08
- 512 **7.1.4 Identifying Metric Context**
- 513 The considerations for identifying the context of a metric are provided in the following sections.

514 7.1.4.1 General Requirements

- 515 Each instance of CIM_BaseMetricDefinition shall be associated with at least one instance of
- 516 CIM_ManagedElement through the CIM_MetricDefForME association. If the CIM_BaseMetricValue
- 517 instance models a metric with the current data access type, the CIM_BaseMetricValue instance shall be
- 518 associated with exactly one instance of CIM_ManagedElement through the CIM_MetricForME
- 519 association.

520 **7.1.4.2 Breakdown Dimensions (Optional)**

- 521 If multiple instances of CIM_BaseMetricValue are available concurrently for a given instance of
- 522 CIM_ManagedElement, where the instances of CIM_BaseMetricValue are associated with the same
- 523 instance of CIM_BaseMetricDefinition through instances of the CIM_MetricValue association and the time 524 frame for which the metric values are recorded overlaps in whole or in part, the requirements specified in
- 525 this subclause shall be met.
- 526 The CIM_BaseMetricDefinition.BreakdownDimensions property shall not be NULL.
- 527 At most, one instance of CIM_BaseMetricValue may have null values for the BreakdownDimension and 528 BreakdownValue properties.
- 529 If the incorporating profile that specifies the CIM_BaseMetricDefinition is a DMTF Management Profile,
- and a value of the CIM_BaseMetricDefinition.BreakdownDimensions identifies a CIM class, the value
- 531 shall be formatted as:
- 532 <schemaName>"_"<simpleClassName>
- 533 as specified in <u>DSP0004</u>.
- 534 If the incorporating profile that specifies the CIM_BaseMetricDefinition is a DMTF Management Profile,
- and a value of the CIM_BaseMetricDefinition.BreakdownDimensions does not identify a CIM class, the
 value shall be formatted as follows:
- 537 "DMTF" <unique identifier>

- 539 If the incorporating profile is not a DMTF Management Profile, each value of the
- 540 CIM_BaseMetricDefinition.BreakdownDimensions property shall be formatted as follows:
- 541 < OrgID > : < LocalID >, where < OrgID > and < LocalID > are separated by a colon (:) and
- 542 < OrgID > shall include a copyrighted, trademarked, or otherwise unique name that is owned by the
- 543 business entity that is creating or defining the value or that is a registered ID assigned to the
- 544 business entity by a recognized global authority. In addition, to ensure uniqueness, < OrgID > shall 545 not contain a colon (:). If using this algorithm, the first colon to appear in the value shall appear
- 546 between < OrgID > and < LocalID >. < LocalID > is chosen by the business entity and shall be used 547 uniquely.
- 548 If the CIM_BaseMetricValue.BreakdownValue identifies a CIM instance, the
- 549 CIM_BaseMetricValue.BreakdownValue property shall be formatted as a WBEM URI (as defined in DSP0207) that identifies the CIM instance.
- 551 If the value of the CIM_BaseMetricValue.BreakdownDimension property is not NULL, it shall be one of
- the values contained in the CIM_BaseMetricDefinition.BreakdownDimensions property of the associated
- 553 instance of CIM_BaseMetricDefinition. If the CIM_BaseMetricValue.BreakdownDimension property is
- 554 NULL, the CIM_BaseMetricValue.BreakdownValue property shall be NULL.

555 **7.1.5 Gathering Type**

- 556 If values for an instance of CIM_BaseMetricDefinition are gathered through online monitoring, the
- 557 CIM_BaseMetricDefinition.GatheringType property shall have a value of 3 (Periodic) or 2 (OnChange). If 558 values for an instance of CIM_BaseMetricDefinition are gathered through snapshot monitoring, the
- 559 CIM_BaseMetricDefinition.GatheringType property shall have a value of 4 (OnRequest).

560 **7.2 Modeling Metric Access Types**

561 This section details requirements for modeling different metric access types. The requirements stated in 562 this section for the CIM_BaseMetricDefinition and CIM_BaseMetricValue classes shall also apply to the 563 CIM_AggregationMetricDefinition and CIM_AggregationMetricValue subclasses, respectively.

7.2.1 Modeling Current Data Access Type (Optional)

565 Metrics with an access type of current data may be supported. If metrics with an access type of current 566 data are modeled, the CIM_BaseMetricDefinition and CIM_BaseMetricValue classes shall be used as 567 defined in 10.10 and 10.12, respectively.

568 7.3 Modeling Metric Time Scope

- 569 This section details requirements for modeling metrics with common time scopes. The requirements 570 stated in this section for CIM_BaseMetricDefinition and CIM_BaseMetricValue shall also apply to the
- 571 CIM_AggregationMetricDefinition and CIM_AggregationMetricValue subclasses, respectively.

572 7.3.1 Modeling Instantaneous Metrics (Optional)

- 573 Instantaneous metrics may be modeled. If instantaneous metrics are modeled, the
- 574 CIM_BaseMetricDefinition and CIM_BaseMetricValue classes shall be used as defined in 10.6 and 10.11, 575 respectively.

576 **7.3.2 Modeling Interval Metrics (Optional)**

577 Interval metrics may be modeled. If interval metrics are modeled, the CIM_BaseMetricDefinition and 578 CIM_BaseMetricValue classes shall be used as defined in 10.7 and 10.13, respectively.

579 7.3.3 Modeling Interval Metrics (Optional)

580 Startup interval metrics may be modeled. If interval metrics are modeled, the CIM_BaseMetricDefinition 581 and CIM_BaseMetricValue classes shall be used as defined in 10.8 and 10.14, respectively.

582 7.4 Modeling Metric Value Formulation

583 This section details requirements for modeling metrics with common value formulations.

584 7.4.1 Modeling Summation Metrics (Optional)

585 Summation metrics may be modeled. If summation metrics are modeled, the CIM_BaseMetricDefinition 586 and CIM_BaseMetricValue clases shall be used as defined in 10.9 and 10.15, respectively.

587 7.4.2 Modeling Aggregation Metrics (Optional)

Aggregation metrics may be modeled. When aggregation metrics are modeled, the requirements
 specified in this section shall be met. An instance of CIM_AggregationMetricDefinition shall define the
 aggregation metric. An instance of CIM_AggregationMetricValue shall exist for each aggregation metric
 value.

592 **7.4.2.1 Modeling Low Watermark Metrics (Optional)**

593 If a low watermark metric is modeled, the instance of CIM_AggregationMetricDefinition that defines the 594 metric shall be implemented as defined in 10.2.

595 7.4.2.2 Modeling High Watermark Metrics (Optional)

596 If a high watermark metric is modeled, the instance of CIM_AggregationMetricDefinition that defines the 597 metric shall be implemented as defined in 10.3.

598 **7.5 Relationship between Aggregation and Base Metrics**

599 If an aggregation metric that is defined by an instance of CIM_AggregationMetricDefinition reports a value

derived from a base metric that is modeled with an instance of CIM_BaseMetricDefinition, the instance of

601 CIM_AggregationMetricDefinition may be associated with the instance of CIM_BaseMetricDefinition

through an instance of CIM_ConcreteDependency, where the instance of CIM_ConcreteDependency is
 as defined in 10.17. If the aggregation metric value modeled with an instance of

604 CIM_AggregationMetricValue is identical to a base metric value for the base metric definition from which 605 the aggregation metric is derived, the instance of CIM AggregationMetricValue may be associated with

the aggregation methods derived, the instance of CIM_Aggregation method are than be associated with
 the CIM_BaseMetricValue through an instance of CIM_ConcreteDependency that is implemented as
 defined in 10.18.

608 7.6 Constraints on Metric Values for Controllable Metrics

- The ability to control the collection of a metric defined by an instance of CIM_BaseMetricDefinition for a managed element represented by an instance of CIM_ManagedElement may be supported.
- 611 If the value of the MetricCollectionEnabled property of the CIM_MetricDefForME instance that associates
- an instance of CIM_BaseMetricDefinition with an instance of CIM_ManagedElement has the value 3
- 613 (Disabled), an instance of CIM_BaseMetricValue shall not be associated with the
- 614 CIM_BaseMetricDefinition through CIM_MetricInstance where the instance of CIM_BaseMetricValue is
- associated with the CIM_ManagedElement instance through CIM_MetricForME and the value of the
- 616 CIM_BaseMetricValue.Volatile property is 2 (Enabled).

- 617 The value of the RecordedSince property of an instance of CIM_MetricDefForME shall not reflect a value
- 618 earlier in time than the time when the MetricCollectionEnabled property of the instance of
- 619 CIM_MetricDefForME last transitioned from a value of 3 (Disabled) to 2 (Enabled).

For an instance of CIM_BaseMetricValue that is associated with an instance of CIM_BaseMetricDefinition through CIM_MetricInstance and that is associated with an instance of CIM_ManagedElement through the CIM_MetricForME association, if an instance of CIM_BaseMetricValue has a value of 2 (Enabled) for the Volatile property, the value of the TimeStamp property or the value calculated by subtracting the value of the Duration property from the value of the TimeStamp property shall not specify a point in time earlier than the value of the RecordedSince property of the instance of CIM_MetricDefForME that associates the instance of CIM_BaseMetricDefinition to the instance of CIM_ManagedElement.

627 8 Methods

628 This section details the requirements for supporting intrinsic operations and extrinsic methods for the CIM

elements defined by this profile. For the extrinsic methods defined in clauses 8.1 through 8.5, the

- requirements pertaining to the CIM_BaseMetricDefinition and CIM_BaseMetricValue classes shall also
- apply to the CIM_AggregationMetricDefinition and CIM_AggregationMetricValue subclasses, respectively.

632 8.1 CIM_MetricService.ShowMetrics()

The ShowMetrics() method provides the ability to query for metrics that a server-side implementation is able to collect, as well as whether or not collection of the metric is currently enabled.

- The ShowMetrics() method's return code values shall be as specified in Table 2 where the method
 execution behavior matches the return code description. The ShowMetrics() method's parameters are
 specified in Table 3.
- specified in Table 5.
- 638 No standard messages are defined for this method.
- 639

Table 2 – CIM_MetricService.ShowMetrics() Method: Return Code Values

Value	Description
0	Operation completed successfully
1	Operation unsupported
2	Failed

Qualifiers	Name	Туре	Description/Values
IN	Subject	CIM_ManagedElement REF	Reference to the CIM_ManagedElement for which metrics will be reported
IN	Definition	CIM_BaseMetricDefinition REF	Reference to the CIM_BaseMetricDefinition to query for values of
OUT	ManagedElements	CIM_ManagedElement REF[]	Array of references to instances of CIM_ManagedElement for which the metric identified by the Definition parameter is being collected
OUT	DefinitionList	REF[]	Array of references to instances of CIM_BaseMetricDefinition defining metrics being collected for the CIM_ManagedElement instance identified by the Subject parameter
OUT	MetricNames	string[]	Array of metric names for the instances of CIM_BaseMetricDefinition specified by the DefinitionList parameter
OUT	MetricCollectionEnabled	uint16[]	Array of values indicating whether or not a metric is being collected

641 8.1.1 CIM_MetricService.ShowMetrics() Conditional Support

If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities
contains the value 4 (ShowMetrics), the ShowMetrics() method shall be implemented and shall not return
the value 1 (Not Supported).

If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities does
 not contain the value 4 (ShowMetrics), the ShowMetrics() method shall not be implemented or shall
 always return the value 1 (Not Supported).

always return the value 1 (Not Supported).

648 8.2 CIM_MetricService.ShowMetricsByClass()

649 The ShowMetricsByClass() method provides the ability to query for metrics that a server-side 650 implementation is able to collect, as well as whether or not collection of the metric is currently enabled.

The ShowMetricsByClass() method's return code values shall be as specified in Table 4 where the

method execution behavior matches the return code description. The ShowMetricsByClass() method's
 parameters are specified in Table 5.

No standard messages are defined for this method.

655

Table 4 – CIM_MetricService.ShowMetricsByClass() Method: Return Code Values

Value	Description
0	Operation completed successfully
1	Operation unsupported
2	Failed

Qualifiers	Name	Туре	Description/Values
IN	Subject	CIM_ManagedElement REF	Identifies a CIM class for which metrics will be reported
IN	Definition	CIM_BaseMetricDefinition REF	Reference to the CIM_BaseMetricDefinition to query for values of
OUT	DefinitionList	REF[]	Array of references to instances of CIM_BaseMetricDefinition defining metrics being collected for the CIM class identified by the Subject parameter
OUT	MetricNames	string[]	Array of metric names for the instances of CIM_BaseMetricDefinition specified by the DefinitionList parameter
OUT	MetricCollectionEnabled	uint16[]	Array of values indicating whether or not a metric is being collected

Table 5 – CIM_MetricService.ShowMetricsByClass() Method: Parameters

657 8.2.1 CIM_MetricService.ShowMetricsByClass() Conditional Support

If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities
 contains the value 5 (ShowMetricsByClass), the ShowMetricsByClass() method shall be implemented
 and shall not return the value 1 (Not Supported).

661 If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities does 662 not contain the value 5 (ShowMetricsByClass), the ShowMetricsByClass() method shall not be

663 implemented or shall always return the value 1 (Not Supported).

664 8.3 CIM_MetricService.ControlMetrics()

- 665 The ControlMetrics() method provides the ability to enable or disable the collection of:
- a metric for all instances of CIM_ManagedElement
- all metrics for a single CIM_ManagedElement instance
- a single metric for a single CIM_ManagedElement instance
- 669 The ControlMetrics() method's return code values shall be as specified in Table 6 where the method
- 670 execution behavior matches the return code description. The ControlMetrics() method's parameters are 671 specified in Table 7.
- 672 No standard messages are defined for this method.
- 673

Table 6 – CIM_MetricService.ControlMetrics() Method: Return Code Values

Value	Description	
0	Operation completed successfully	
1	Operation unsupported	
2	Failed	

Qualifiers	Name	Туре	Description/Values
IN	Subject	CIM_ManagedElement REF	Reference to the CIM_ManagedElement for which metrics will be controlled
IN	Definition	CIM_BaseMetricDefinition REF	Reference to the CIM_BaseMetricDefinition for which collection is to be enabled or disabled
IN, REQ	MetricCollectionEnabled	uint16	Value indicating whether or not the metric is collected

675 8.3.1 CIM_MetricService.ControlMetrics() Conditional Support

676 If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities 677 contains the value 2 (ControlMetrics), the ControlMetrics() method shall be implemented and shall not 678 return the value 1 (Not Supported).

If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities does
 not contain the value 2 (ControlMetrics), the ControlMetrics() method shall not be implemented or shall
 always return the value 1 (Not Supported).

682 8.3.2 Parameter Validation

If the Subject parameter is NULL and the instance of CIM_BaseMetricDefinition that is identified by the
 Definition parameter is not identified by a value of the ControllableMetrics property of the associated
 instance of CIM_MetricServiceCapabilities where the corresponding array index of the
 MetricsControlTypes property of the CIM_MetricServiceCapabilities instance has the value 3 (Bulk) or 4

(Both), the method shall return a value of 2 (Failed).

688 If the Definition parameter is NULL and the instance of CIM_ManagedElement identified by the Subject 689 parameter is not identified by a value of the ControllableManagedElement property of the associated

690 instance of CIM MetricServiceCapabilities where the corresponding array index of the

691 ManagedElementControlTypes property of the CIM_MetricServiceCapabilities instance has the value 3 692 (Bulk) or 4 (Both), the method shall return a value of 2 (Failed).

- 693 If both the Subject and Definition parameters are non-null, the method shall return a value of 2 (Failed) if 694 neither of the following conditions is met:
- 695 The instance of CIM_ManagedElement identified by the Subject parameter is identified by a • 696 value of the ControllableManagedElements property of the associated instance of 697 CIM_MetricServiceCapabilities, where the corresponding array index of the ManagedElementControlTypes property of the CIM_MetricServiceCapabilities instance has a 698 699 value of 2 (Discrete), and the instance of CIM BaseMetricDefinition identified by the Definition 700 parameter is identified by a value of the ControllableMetrics property of the associated instance of CIM MetricServiceCapabilities, where the corresponding array index of the 701 702 MetricsControlTypes property of the CIM MetricServiceCapabilities instance has a value of 2 (Discrete). 703 704 The instance of CIM_BaseMetricDefinition identified by the Definition parameter is identified by • a value of the ControllableMetrics property of the associated instance of 705 706 CIM_MetricServiceCapabilities, where the corresponding array index of the MetricsControlTypes property of the CIM_MetricServiceCapabilities instance has a value of 2 707 708 (Discrete) and no instances of CIM ManagedElement that are associated with the 709 CIM BaseMetricDefinition through the CIM MetricDefForME are identified by a value of the
 - 10 ControllableManagedElements property of the associated instance of
- 710 ControllableManagedElements property of the associated inst 711 CIM MetricServiceCapabilities.

712NOTE: The effect of the second condition is to allow the advertisement of support for controlling the713collection of every metric value for a CIM_BaseMetricDefinition instance without having to explicitly list714each CIM_ManagedElement instance in the ControllableManagedElements property.

715 8.4 CIM_MetricService.ControlMetricsByClass()

- 716 The ControlMetricsByClass() method provides the ability to enable or disable the collection of:
- a metric for all instances of a specific CIM class
- all metrics for all instances of a specific CIM class
- a single metric for a single CIM_ManagedElement

The ControlMetricsByClass() method's return code values shall be as specified in Table 8 where the
 method execution behavior matches the return code description. The ControlMetricsByClass() method's
 parameters are specified in Table 9.

723 No standard messages are defined for this method.

724

Table 8 – CIM_MetricService.ControlMetricsByClass() Method: Return Code Values

Value	Description	
0	Operation completed successfully	
1	Operation unsupported	
2	Failed	

725

Table 9 – CIM_MetricService.ControlMetricsByClass() Method: Parameters

Qualifiers	Name	Туре	Description/Values
IN	Subject	CIM_ManagedElement REF	Reference to the CIM class for which metrics will be controlled
IN	Definition	CIM_BaseMetricDefinition REF	Reference to the CIM_BaseMetricDefinition for which collection is to be enabled or disabled
IN, REQ	MetricCollectionEnabled	uint16	Value indicating whether the metric is to be enabled or disabled

726 8.4.1 CIM_MetricService.ControlMetricsByClass() Conditional Support

727 If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities 728 contains the value 3 (ControlMetricsByClass), the ControlMetricsByClass() method shall be implemented

and shall not return the value 1 (Not Supported).

If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities does
 not contain the value 3 (ControlMetricsByClass), the ControlMetricsByClass() method shall not be

implemented or shall always return the value 1 (Not Supported).

733 8.4.2 Parameter Validation

734 If the Subject parameter is NULL and the instance of CIM_BaseMetricDefinition that is identified by the 735 Definition parameter is not identified by a value of the ControllableMetrics property of the associated

736 instance of CIM MetricServiceCapabilities where the corresponding array index of the

737 MetricsControlTypes property of the CIM MetricServiceCapabilities instance has the value 3 (Bulk) or 4

738 (Both), the method shall return a value of 2 (Failed).

739 8.5 CIM_MetricService.GetMetricValues()

740 The GetMetricValues() method provides the ability to query for metric values.

The GetMetricValues() method's return code values shall be as specified in Table 10 where the method execution behavior matches the return code description. The GetMetricValues() method's parameters are

specified in Table 11.

No standard messages are defined for this method.

Table 10 – CIM_MetricService.GetMetricValues() Method: Return Code Values

Value	Description	
0	Operation completed successfully	
1	Operation unsupported	
2	Failed	

```
746
```

745

Table 11 – CIM_MetricService.GetMetricValues() Method: Parameters

Qualifiers	Name	Туре	Description/Values
IN	Definition	CIM_BaseMetricDefinition REF	Reference to the CIM_BaseMetricDefinition to query for values
IN	Range	uint16	Identifies how the values are selected
IN	Count	uint16	Identifies the maximum number of instances to return
OUT	Values	CIM_BaseMetricValue REF[]	Array of references to instances of CIM_BaseMetricValue corresponding to the CIM_BaseMetricValue instances that match the query constraints identified by the input parameters

747 8.5.1 CIM_MetricService.GetMetricValues() Conditional Support

- If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities
 contains the value 6 (GetMetricValues), the GetMetricValues() method shall be implemented and shall
 not return the value 1 (Not Supported).
- 751 If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities does 752 not contain the value 6 (GetMetricValues), the GetMetricValues() method shall not be implemented or 753 aball always rature the value 1 (Net Supported)
- shall always return the value 1 (Not Supported).

754 **8.6 Profile Conventions for Operations**

- For each profile class (including associations), the implementation requirements for operations, including those in the following default list, are specified in class-specific subclauses of this clause.
- 757 The default list of operations is as follows:
- GetInstance
- Associators
- 760 AssociatorNames
- 761 References

Base Metrics Profile

- 762 ReferenceNames
- EnumerateInstances
- Find the second s

765 8.7 CIM_AggregationMetricDefinition

- All operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.
- 767 NOTE: Related profiles may define additional requirements on operations for the profile class.

768 8.8 CIM_AggregationMetricValue

- All operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.
- 770 NOTE: Related profiles may define additional requirements on operations for the profile class.

771 8.9 CIM_BaseMetricDefinition

- All operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.
- 773 NOTE: Related profiles may define additional requirements on operations for the profile class.

774 8.10 CIM_BaseMetricValue

- All operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.
- 776 NOTE: Related profiles may define additional requirements on operations for the profile class.

777 8.11 CIM_ConcreteDependency

- Table 12 lists implementation requirements for operations. If implemented, these operations shall be
- implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 12, all operations
 in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.
- 781 NOTE: Related profiles may define additional requirements on operations for the profile class.
- 782

Table 12 – Operations: CIM_ConcreteDependency

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

783 **8.12 CIM_ElementCapabilities**

Table 13 lists implementation requirements for operations. If implemented, these operations shall be
 implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 13, all operations
 in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.

787 NOTE: Related profiles may define additional requirements on operations for the profile class.

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

789 8.13 CIM_HostedService

790 Table 14 lists implementation requirements for operations. If implemented, these operations shall be

implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 14, all operations
 in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.

793 NOTE: Related profiles may define additional requirements on operations for the profile class.

794

Table 14 – Operations: CIM_HostedService

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

795 **8.14 CIM_MetricDefForME**

Table 15 lists implementation requirements for operations. If implemented, these operations shall be

implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 15, all operations
 in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.

799 NOTE: Related profiles may define additional requirements on operations for the profile class.

800

Table 15 – Operations: CIM_MetricDefForME

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

8.15 CIM MetricForME 801

802 Table 16 lists implementation requirements for operations. If implemented, these operations shall be implemented as defined in DSP0200. In addition, and unless otherwise stated in Table 16, all operations 803 in the default list in 8.6 shall be implemented as defined in DSP0200.

- 804
- NOTE: 805 Related profiles may define additional requirements on operations for the profile class.

806

Table 16 – Operations: CIM_MetricForME

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

8.16 CIM_MetricInstance 807

- 808 Table 17 lists implementation requirements for operations. If implemented, these operations shall be
- implemented as defined in DSP0200. In addition, and unless otherwise stated in Table 17, all operations 809 810 in the default list in 8.6 shall be implemented as defined in DSP0200.
- 811 NOTE: Related profiles may define additional requirements on operations for the profile class.
- 812

Table 17 – Operations: CIM_MetricInstance

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

8.17 CIM MetricService 813

814 All operations in the default list in 8.6 shall be implemented as defined in DSP0200.

8.18 CIM_MetricServiceCapabilities 815

816 All operations in the default list in 8.6 shall be implemented as defined in DSP0200.

817 8.19 CIM_ServiceAffectsElement

Table 18 lists implementation requirements for operations. If implemented, these operations shall be

819 implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 18, all operations

820 in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.

821 NOTE: Related profiles may define additional requirements on operations for the profile class.

822

Table 18 – Operations: CIM_ServiceAffectsElement

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

823 9 Use Cases (Informative)

824 This section contains object diagrams and use cases for the *Base Metrics Profile*.

825 9.1 Instructions Executed per Second

This section contains object diagrams showing several implementations of metrics related to the execution of processor instructions. A management client can use each different type of metric provided to determine the instructions executed per second (IEPS) for the operating system.

829 9.1.1 Interval Metrics

830 Figure 2 presents an object diagram for an implementation of an interval metric showing the instructions 831 executed per second for an operating system image. There is one instance of the BaseMetricValue class with a TimeStamp property value of 07:25:00 A.M. at 9/4/2006, a Duration property value of 60 seconds 832 and a metric value of 100 million, meaning that the instrumented server has executed 100 million 833 834 instructions on 9/4/2006 between 07:24:00 A.M. and 07:25:00 A.M. The measured element in this 835 example is an instance of CIM_OperatingSystem. A management client could calculate the average instructions executed per second from 07:24:00 A.M. to 07:25:00 A.M. by dividing the total number of 836 837 instructions (100 million) by the duration (60 seconds).

- The CIM_BaseMetricDefinition.Id property contains a UUID that is chosen by the metrics provider.
- The DataType is set to 13 (uint64), which means that the metric values associated to this metric definition instance are intended to be of type uint64.
- TimeScope 3 (Interval) means that the metric values are related to a time interval. The values of the
- TimeStamp and Duration properties indicate that the monitored interval is 09/04/2006 7:24 A.M. UTC
- 843 through 09/04/2006 7:25 A.M. UTC. The MetricValue property indicates that the operating system has
- executed 100 million instructions between 7:24:00 A.M. UTC and 7:25:00 A.M. UTC.
- 645 GatheringType 3 (Periodic) means that the underlying gathering infrastructure is capturing new counters 646 periodically. How frequently the metric is captured is not indicated. An example would be once a minute.



Figure 2 – Interval Metrics

850 9.1.2 Instantaneous Counter

851 The object diagram in Figure 3 shows a possible implementation of an instantaneous metric reporting the

number of instructions executed. There is exactly one instance of class CIM_BaseMetricValue. The client 852

has executed a GetInstance operation at one minute intervals to query the current values of the metric. 853

The object diagram shows the last retrieved instance using the standard notation. The box with the 854

rounded corners shows the same instance retrieved one minute earlier. A management client can 855 calculate the average IEPS by calculating the delta between the MetricValue properties for the two

- 856 instances and dividing it by the delta between the TimeStamp properties of the two instances.
- 857

858



860

859



861 9.1.3 Instantaneous Gauge

Figure 4 shows an object diagram in which average instructions per second are directly instrumented.

The underlying system provides a metric that corresponds to the average number of instructions per second. However, it does not provide information about the duration over which the average was calculated. This is sometimes known as an instantaneous average.

The ProgrammaticUnits property indicates that the metric reports millions of instructions per second. The CIM_BaseMetricDefinition.TimeScope property indicates that the metric is an interval metric. The CIM_BaseMetricValue.Duration property indicates that there is no precision to the reported interval duration. The current values of the properties of the CIM_BaseMetricValue instance indicate that, as of 07:25:00 A.M. at 9/4/2006, an average of 100 million instructions were executed per second.

871

Met	ricInstance
BaseMetricDefinition	BaseMetricValue
Id : "xyz:87654321" Name : "xyz:Instructions" DataType : 13 (uint64) ProgrammaticUnits : "count / second * 10^6" IsContinuous : true ChangeType : 4 (Gauge) TimeScope : 3 (Interval) GatheringType : 4 (OnRequest)	MetricDefinitionId : "xyz:87654321" MeasuredElementName : "tux4ever image" TimeStamp : "20060904072500.000000+000" Duration : "***********************************
MetricDefForME	MetricForME OperatingSystem

873

872

Figure 4 – Instantaneous Gauge

9.2 Object Diagram for Startup Interval Time Scope

A value of 4 (StartupInterval) for the TimeScope property indicates that the metric applies to an interval

that began at the startup of the measured resource. The example in Figure 5 shows that at 07:25:00 A.M.

on 09/04/2006, the associated application system "DB2 V9.1 on tux4ever" was running for a duration of

878 977 days and 5 hours, consuming 100 million resources. The associated metric is "InstructionsExecuted",

879 with a unit of "Million Count" of instructions.



881

Figure 5 – Usage Example for Startup Interval Time Scope

882 9.3 Metric Definition for Multiple Instances of CIM_ManagedElement

Figure 6 is an object diagram for an implementation that reports the same metric for two managed elements. metval1 and metval2 report the standard metric "xyz:InstructionsPerSecond" for cpu1 and cpu2, respectively.



888

Figure 6 – Common Metric Definition for Multiple Instances of CIM_ManagedElement

9.4 Controllable Metrics 889

890 Figure 7 shows an object diagram for an implementation in which a single metric, represented by the 891 CIM BaseMetricDefinition instance bmd1, is available for two processors, represented by CIM Processor 892 instances cpu1 and cpu2. Enabling and disabling the collection of the metric for cpu1 and cpu2 is 893 performed separately. The capabilities for controlling metric collection are indicated by capabilities1. The 894 value of the ControllableMetrics property is bmd1, which indicates that some amount of control over metric collection for values of bmd1 is supported. The value of the MetricControlTypes property is 2 895 896 (Discrete), which indicates that metric collection can be controlled for individual values. The value of the ControllableManagedElements property is NULL or empty. The absence of a specific list of 897 CIM ManagedElement instances associated with bmd1 indicates that controlling metric collection for all 898 metric values of bmd1 is supported. The CIM ServiceAffectsElement associations between the 899 CIM MetricService instance and the CIM BaseMetricDefinition instances have been elided. 900



902

903

Figure 7 – Advertising Support for Discrete Controllable Metrics

- 904 Figure 8 shows an object diagram for an implementation in which a single metric, represented with the
- 905 CIM_BaseMetricDefinition instance bmd1, is available for two processors, represented by the
- 906 CIM_Processor instances cpu1 and cpu2.

907 The ability to control metrics supported by the implementation shown in Figure 8 is identical to those of 908 the implementation shown in Figure 7. Figure 8 shows an alternate method of advertising the support.

- 909 The value of the ControllableMetrics property is bmd1, which indicates that some amount of control over
- 910 metric collection for values of bmd1 is supported. The value of the MetricControlTypes property is 2
- 911 (Discrete), which indicates that metric collection can be controlled for individual values. The value of the
- 912 ControllableManagedElements property is cpu1 and cpu2, which indicates that some amount of control
- 913 over metrics for cpu1 and cpu2 is supported.
- In the object diagram shown in Figure 8, collection of the metric for cpu1 has been disabled. This is
- 915 indicated by the value of the MetricCollectionEnabled property of the instance of CIM_MetricDefForME
- that associates bmd1 with cpu1. The CIM_ServiceAffectsElement associations between the
- 917 CIM_MetricService instance and the CIM_BaseMetricDefinition instances have been elided.



918

919

Figure 8 – Discrete Controllable Metrics (Before Enable)
- 920 Figure 9 shows an object diagram for the system shown in Figure 8. The
- 921 CIM_MetricService.ControlMetrics() method has been used to enable the collection of the metric
- 922 represented by the bmd1 instance for cpu1. The CIM_ServiceAffectsElement associations between the
- 923 CIM_MetricService instance and the CIM_BaseMetricDefinition instances have been elided.



924 925

Figure 9 – Discrete Controllable Metrics (After Enable)

Base Metrics Profile

- 926 Figure 10 shows an object diagram for an implementation where two metrics, represented by the
- 927 CIM_BaseMetricDefinition instances bmd1 and bmd2, are available for two processors, represented by
- 928 CIM_Processor instances cpu1 and cpu2. The collection of all metric values for the bmd2 instance is
- 929 controlled as a single operation. The collection of metric values for the bmd1 instance is controlled 930 discretely for each metric value. In the object diagram shown in Figure 10, collection of the metric
- 930 discretely for each metric value. In the object diagram shown in Figure 10, collection of the metric 931 represented by bmd2 has been disabled. This is indicated by the value of the MetricCollectionEnabled
- property of the instances of CIM_MetricDefForME that associate bmd2 with cpu1 and cpu2. The
- 933 CIM_ServiceAffectsElement associations between the CIM_MetricService instance and the
- 934 CIM_BaseMetricDefinition instances have been elided.

935



937

Figure 10 – Bulk Controllable Metrics by Definition

DSP1053

- 938 Figure 11 shows an object diagram for an implementation in which two metrics, represented by the
- 939 CIM_BaseMetricDefinition instances bmd1 and bmd2, are available for three processors, represented by
- 940 CIM_Processor instances cpu1, cpu2, and cpu3. The collection of all metric values for bmd2 is controlled
- as a single operation. The collection of metric values for bmd1 is controlled discretely for each metric
- 942 value. In the object diagram shown in Figure 11, collection of metric values for bmd2 has been disabled.
- 943 This is indicated by the value of the MetricCollectionEnabled property of the instances of
- 944 CIM_MetricDefForME that associate bmd2 with cpu3 and cpu2. The CIM_ServiceAffectsElement
- associations between the CIM_MetricService instance and the CIM_BaseMetricDefinition instances have
 been elided.



Figure 11 – Bulk Controllable Metrics by Managed Element

Base Metrics Profile

- 949 Figure 12 shows an object diagram for an implementation in which a single metric is available for three
- 950 processors, represented by instances of subclasses of CIM_Processor cpu1, cpu2, and cpu3. Two
- 951 instances of CIM_BaseMetricDefinition (bmd1 and bmd2) define the same standard metric
- 952 "xyz:InstructionsPerSection". Multiple instances of the CIM_BaseMetricDefinition class are required in
 953 order to represent the separate control points for collection of the metric values. The collection of bmd2 is
- controlled for all instances of the yyy_Processor class as a bulk operation. Control of the collection of the
- 955 metric value defined by bmd1 for cpu1 is not supported. The CIM_ServiceAffectsElement associations
- 956 between the CIM MetricService instance and the CIM BaseMetricDefinition instances have been elided.
- 957



958

Figure 12 – Bulk Controllable Metrics by Class

960 9.5 Aggregation Metrics

Figure 13 shows an object diagram for an implementation that supports reporting a high watermark for the number of instructions per second executed on a processor. The maximum value in the approximate interval from 12/28/2005 through 11/04/2006 occurred on 09/04/2006 at 7:25 A.M. UTC.



964

965

Figure 13 – Aggregation Metric without Base

966 Figure 14 shows an object diagram for an implementation that provides the same function as the

967 implementation shown in Figure 13 with the additional functionality of supporting the underlying base metric. The information that bmd1 is the base metric for amd1 is conveyed by the instance of 968

969

CIM_ConcreteDependency that associates them. In this implementation, long-term monitoring is 970 supported for bmd1; hence, the instance metval1 exists even though it represents historical data.



972

Figure 14 – Aggregation Metric with Base

973 9.6 Metric Context

974 Figure 15 illustrates the use of breakdown dimensions to differentiate among multiple instances of

975 CIM_BaseMetricValue that provide instances of the same metric definition. metval1 and metval2 are

976 instances of the metric that indicate the instructions per second consumed by process1 from cpu1 and

977 cpu2, respectively. metval3 provides information about the total instructions per second utilized by

978 process1 from all processors.





981

Figure 15 – Metric Context

982 9.7 Find All Metric Definitions for a Managed Element

- 983 A client can find all of the metric definitions available for a Managed Element as follows:
- Starting at the instance of CIM_ManagedElement, find all instances of
 CIM_BaseMetricDefinition associated with the CIM_ManagedElement instance through the
 CIM_MetricDefForME association.

987 9.8 Find the Metric Value for a Managed Element

- 988 Given an instance of CIM_BaseMetricDefinition that is associated with the CIM_ManagedElement 989 instance through a CIM_MetricDefForME association, a client can find the metric value for the 990 CIM ManagedElement as follows:
- 991 1) Find the instance of CIM_MetricDefForME that associates the CIM_BaseMetricDefinition with
 992 the CIM_ManagedElement instance.
- 993 2) If the value of the MetricCollectionEnabled property of the instance of CIM_MetricDefForME
 994 association found in the previous step is 2 (Enabled):
- 995 a) Find all instances of CIM_BaseMetricValue associated with the CIM_BaseMetricDefinition
 996 through the CIM_MetricInstance association.
- 997b)Find all instances of CIM_BaseMetricValue associated with the CIM_ManagedElement998instance through CIM_MetricForME.
- 999 c) Find the instance of CIM_BaseMetricValue that is the intersection of the two result sets by 1000 finding matching InstanceID property values.
- 1001 3) Otherwise, metric collection is disabled and a current data metric value is not available.

1002 9.9 Find a Standard Metric for a Managed Element

- 1003 Given a string value corresponding to the unique identifier of a standard metric, a client can find the 1004 standard metric value for an instance of CIM_ManagedElement as follows:
- 10051)Use the steps in 9.6 to find all metric definitions available for the instance of
CIM_ManagedElement.
- 10072)For each instance of CIM_BaseMetricDefinition returned, determine if the Name property1008matches the string identifier. If there is a match, use the steps in 9.8 to find the metric value.
- 10093)If a matching Name property is not found, the standard metric is not supported for the instance1010of CIM_ManagedElement.

1011 9.10 Retrieve a Metric Value

- 1012 A client can retrieve a metric value as follows:
- 1013 1) Using the steps in 9.9, find the instance of CIM_BaseMetricValue that reports the metric.
- 10142)Invoke GetInstance to query the current values of properties of the CIM_BaseMetricValue1015instance.

10169.11 Find All Metrics Available for a Managed Element within an Enumeration1017Scope

- 1018 Given an instance of CIM_ManagedElement, a client can find all of the metrics available for an instance 1019 of CIM_ManagedElement as follows:
 - 1) Enumerate all instances of CIM_MetricService within the enumeration scope.
- 1020a)For each instance of CIM_MetricService, find the instance of1021CIM_MetricServiceCapabilities associated through CIM_ElementCapabilities.
- b) Query the value of the CIM_MetricServiceCapabilities.SupportedMetrics property.
- 1023c)If the array contains the value 4 (Show Metrics), invoke the1024CIM_MetricService.ShowMetrics() method providing the reference to the1025CIM_ManagedElement.
- 1026d)The list of references to CIM_BaseMetricDefinition returned as the value of the Definitions1027parameter identifies instances of CIM_BaseMetricDefinition that are available for the1028CIM_ManagedElement instance.
- 10292)Starting with a reference to the instance of CIM_ManagedElement, find all instances of1030CIM_MetricDefinition that are associated through CIM_MetricDefForME.
- 1031 3) Union the results of d) and 2).

10329.12 Find All Metrics Available within an Enumeration Scope for All Instances of a1033CIM Class

- 1034 Given a CIM class name, a client can find all of the metrics available within an enumeration scope for all 1035 instances of the class as follows:
- 1036 1) Enumerate all instances of CIM_MetricService within the enumeration scope.
- 1037a)For each instance of CIM_MetricService, find the instance of1038CIM_MetricServiceCapabilities associated through CIM_ElementCapabilities.
- b) Query the value of the CIM_MetricServiceCapabilities.SupportedMetrics property.
- 1040c)If the array contains the value 5 (ShowMetricsByClass), invoke the1041CIM_MetricService.ShowMetrics() method providing the reference to the1042CIM_ManagedElement.
- 1043d)The list of references to CIM_BaseMetricDefinition returned as the value of the Definitions1044parameter identifies instances of CIM_BaseMetricDefinition that are available for the1045CIM_ManagedElement instance.
- 1046 2) Enumerate all instances of the CIM class.
- 1047a)For each instance of the CIM class, find all instances of CIM_BaseMetricDefinition that are1048associated through CIM_MetricDefForME.
- 10493)Form a set of instances of CIM_BaseMetricDefinition from the intersection of the instances1050returned by a).
- 1051 4) Union the results of d) and 3).

1063

1064 1065

1066

10529.13 Determine whether a Metric Can Be Discretely Controlled for a Specific1053Managed Element

1054 Given an instance of CIM_BaseMetricDefinition associated to an instance of CIM_ManagedElement 1055 through CIM_MetricDefForME, a client can determine whether the metric can be controlled for the 1056 managed element as follows:

- 10571)Starting with the instance of CIM_BaseMetricDefinition, find the instance of CIM_MetricService1058associated through CIM_ServiceAffectsElement.
- 10592)Find the instance of CIM_MetricServiceCapabilities associated through1060CIM_ElementCapabilities with the instance of CIM_MetricService found in 1).
- 10613)If the following conditions are met, the metric can be discretely controlled for the managed1062element:
 - The CIM_MetricServiceCapabilities.ControllableMetrics property contains a reference to the CIM_BaseMetricDefinition.
 - b) The CIM_MetricServiceCapabilities.MetricControlTypes property contains the value 2 (Discrete) or 4 (Both) at the same array index as the reference in the previous step.
- 1067c)The CIM_MetricServiceCapabilities.ControllableManagedElements property contains a1068reference to the CIM_ManagedElement.
- 1069d)The CIM_MetricServiceCapabilities.ManagedElementControlTypes property contains the
value 2 (Discrete) or 4 (Both) at the same array index as the reference in the previous step.
- 1071 4) Otherwise, the metric can not be discretely controlled for the managed element.

9.14 Enable a Specific Metric for a Specific Managed Element

- 1073 Given an instance of CIM_BaseMetricDefinition that is associated to an instance of
- 1074 CIM_ManagedElement through the CIM_MetricDefForME association, a client can enable a specific 1075 metric for the managed element as follows:
- 1076 1) Use the steps in 9.13 to determine whether the metric can be controlled.
- 10772)Invoke the CIM_MetricService.ControlMetrics() method and specify the reference to the1078CIM_ManagedElement as the value of the Subject parameter, the reference to the1079CIM_BaseMetricDefinition as the value of the Definition parameter, and TRUE as the value of1080the MetricCollectionEnabled parameter.

10819.15 Find All Managed Elements within an Enumeration Scope for which a Metric1082Is Currently Being Collected

- 1083 Given an instance of CIM_BaseMetricDefinition, a client can find all instances of CIM_ManagedElement 1084 for which the metric is available as follows:
- 10851)Find the instance of CIM_MetricService associated with the CIM_BaseMetricDefinition through1086the CIM_ServiceAffectsElement association.
- 10872)Find the instance of CIM_MetricServiceCapabilities associated with the CIM_MetricService1088found in the previous step.
- 10893)Query the value of the SupportedMethods property of the instance of1090CIM_MetricServiceCapabilities found in the previous step to determine if it contains a value of 41091(ShowMetrics):
- a) If the SupportedMethods property contains a value of 4 (ShowMetrics):
- 1093-Invoke the CIM_MetricService.ShowMetrics() method, specifying the reference to the1094CIM_BaseMetricDefinition as the value of the Definition parameter.

- 1095 Upon successful completion of the method, the ManagedElements parameter contains a list of references to CIM ManagedElement instances for which the metric 1096 defined by the CIM BaseMetricDefinition is available. The MetricCollectionEnabled 1097 1098 property indicates whether the metric is currently being collected for the 1099 CIM ManagedElement instance. 1100 If the SupportedMethods property does not contain the value 4, find all instances of 4) CIM_MetricDefForME that reference the CIM_BaseMetricDefinition instance. For each instance 1101 1102 of CIM_MetricDefForME, the Antecedent property identifies a CIM_ManagedElement for which 1103 the metric may be collected and the MetricCollectionEnabled property indicates whether the
- 1104 metric is currently being collected.

1105 **10 CIM Elements**

1106Table 19 shows the instances of CIM Elements for this profile. Instances of the CIM Elements shall be1107implemented as described in Table 19. Sections 7 ("Implementation") and 8 ("Methods") may impose

1108 additional requirements on these elements.

1109

Table 19 – CIM Elements: Base	e Metrics Profile
-------------------------------	-------------------

Element Name	Requirement	Description
Classes		
CIM_AggregationMetricDefinition	Optional	See 10.1, 10.2, and 10.3.
CIM_AggregationMetricValue	Optional	See 10.4.
CIM_BaseMetricDefinition	Optional	See 10.5, 10.6, 10.7, 10.8, 10.9, and 10.10.
CIM_BaseMetricValue	Optional	See 10.11, 10.12, 10.13, 10.15, and 10.16.
CIM_ConcreteDependency	Optional	See 10.17 and 10.18.
CIM_ElementCapabilities	Mandatory	See 10.19.
CIM_HostedService	Mandatory	See 10.20.
CIM_MetricDefForME	Mandatory	See 10.21.
CIM_MetricForME	Conditional	See 10.22.
CIM_MetricInstance	Conditional	See 10.23.
CIM_MetricService	Mandatory	See 10.24.
CIM_MetricServiceCapabilities	Mandatory	See 10.25.
CIM_RegisteredProfile	Mandatory	See 10.26.
CIM_ServiceAffectsElement	Mandatory	See 10.27.
Indications	·	
None defined in this profile		

1110 **10.1 CIM_AggregationMetricDefinition**

1111 CIM_AggregationMetricDefinition defines a metric that can be captured. Table 20 defines the

requirements for instances of CIM_AggregationMetricDefinition. This class is used as a basis for 10.2 and for 10.3.

1114

Table 20 – Class: CIM_AggregationMetricDefinition

Properties	Requirement	Notes
BreakdownDimensions	Optional	None
Calculatable	Optional	None
ChangeType	Mandatory	Matches 5 (Simple Function)
DataType	Mandatory	None
ElementName	Mandatory	Pattern (".+")
GatheringType	Mandatory	None
ld	Mandatory	Кеу
IsContinuous	Optional	None
TimeScope	Optional	None
ProgrammaticUnits	Mandatory	None
Name	Mandatory	See 7.1.3.
SimpleFunction	Mandatory	None

1115 **10.2 CIM_AggregationMetricDefinition (Low Watermark)**

1116 Table 21 defines the requirements for instances of CIM_AggregationMetricDefinition used to define a low 1117 watermark metric. These constraints are in addition to those specified in 10.1.

1118

Table 21 – Class: CIM_AggregationMetricDefinition (Low Watermark)

Properties	Requirement	Notes
SimpleFunction	Mandatory	Matches 2 (Minimum)

1119 **10.3 CIM_AggregationMetricDefinition (High Watermark)**

1120 Table 22 defines the requirements for instances of CIM_AggregationMetricDefinition used to define high 1121 watermark metrics. These constraints are in addition to those specified in 10.1.

1122

Table 22 – Class: CIM_AggregationMetricDefinition (High Watermark)

Properties	Requirement	Notes
SimpleFunction	Mandatory	Matches 3 (Maximum)

1123 10.4 CIM_AggregationMetricValue

1124 CIM_AggregationMetricValue conveys the actual recorded data of a metric that has been maintained.

1125 Table 23 describes the requirements for instances of CIM_AggregationMetricValue.

1126

Table 23 – Class: CIM_AggregationMetricValue

Properties	Requirement	Notes
MetricDefinitionId	Mandatory	None
MetricValue	Mandatory	None
Volatile	Mandatory	None
InstanceID	Mandatory	Кеу
BreakdownDimension	Optional	None
BreakdownValue	Optional	None
AggregationTimeStamp	Mandatory	None
AggregationDuration	Mandatory	None

1127 **10.5 CIM_BaseMetricDefinition**

1128 CIM_BaseMetricDefinition defines a metric that can be captured. Table 24 defines the requirements for 1129 instances of CIM_BaseMetricDefinition. This class is used as a basis for 10.6 to 10.10.

1130

Table 24 – Class: CIM_BaseMetricDefinition

Properties	Requirement	Notes
BreakdownDimensions	Optional	See 7.1.4.
Calculatable	Optional	None
ChangeType	Mandatory	None
DataType	Mandatory	None
ElementName	Mandatory	Pattern (".+")
GatheringType	Mandatory	See 7.1.5.
ld	Mandatory	Кеу
IsContinuous	Optional	None
TimeScope	Optional	None
ProgrammaticUnits	Mandatory	None
Name	Mandatory	See 7.1.3.

1131 **10.6 CIM_BaseMetricDefinition — Instantaneous Metric**

- 1132 Table 25 describes the requirements for using CIM_BaseMetricDefinition to define an Instantaneous
- 1133 Metric. These constraints are in addition to those specified in 10.5.
- 1134

Table 25 – Class: CIM_BaseMetricDefinition – Instantaneous Metric

Properties	Requirement	Notes
IsContinuous	Mandatory	Matches TRUE
TimeScope	Mandatory	Matches 2 (Point)

1135 **10.7 CIM_BaseMetricDefinition — Interval Metric**

- 1136 Table 26 describes the requirements for using CIM_BaseMetricDefinition to define an Interval Metric.
- 1137 These constraints are in addition to those specified in 10.5.
- 1138

Table 26 – Class: CIM_BaseMetricDefinition – Interval Metric

Properties	Requirement	Notes
TimeScope	Mandatory	Matches 3 (Interval)

1139 **10.8 CIM_BaseMetricDefinition — Startup Interval Metric**

- 1140 Table 27 describes the requirements for using CIM_BaseMetricDefinition to define a Startup Interval
- 1141 Metric. These constraints are in addition to those specified in 10.5.
- 1142

Table 27 – Class: CIM_BaseMetricDefinition – Startup Interval Metric

Properties	Requirement	Notes
TimeScope	Mandatory	Matches 4 (Startup Interval)

1143 **10.9 CIM_BaseMetricDefinition — Summation Metric**

1144 Table 28 describes the requirements for using CIM_BaseMetricDefinition to define a Summation Metric.

- 1145 These constraints are in addition to those specified in 10.5.
- 1146

Table 28 – Class: CIM_BaseMetricDefinition – Summation Metric

Properties	Requirement	Notes
ChangeType	Mandatory	Matches 3 (Counter)
DataType	Mandatory	Matches 4 (real32), 5 (real64), 6 (sint16), 7 (sint32), 8 (sint64), 9 (sint8), 11 (unit16), 12 (uint32), 13 (uint64), or 14 (uint8)

1147 **10.10 CIM_BaseMetricDefinition — Current Data**

1148 Table 29 describes the requirements for using CIM_BaseMetricDefinition to define the metric to be used 1149 with current data. These constraints are in addition to those specified in 10.5.

1150

Table 29 – Class: CIM_BaseMetricDefinition – Current Data

Properties	Requirement	Notes
TimeScope	Mandatory	Matches 2 (Point) or 3 (Interval)

1151 **10.11 CIM_BaseMetricValue**

1152 CIM_BaseMetricValue conveys the actual recorded data of a metric. Table 30 describes the requirements 1153 for instances of CIM BaseMetricValue. This class is used as a basis for 10.12 to 10.16.

1154

1155

Table 30 – Class: CIM_BaseMetricValue

Properties	Requirement	Notes
MetricDefinitionId	Mandatory	None
MetricValue	Mandatory	None
Volatile	Mandatory	None
InstanceID	Mandatory	Кеу
BreakdownDimension	Optional	See 7.1.4.
BreakdownValue	Optional	See 7.1.4.
Timestamp	Optional	None
Duration	Optional	None

1156 **10.12 CIM_BaseMetricValue — Current Data**

1157 CIM_BaseMetricValue reports a metric defined using CIM_BaseMetricDefinition. Table 31 describes the

1158 requirements for using CIM_BaseMetricValue to report the metric for current data. These constraints are

in addition to those specified in 10.11.

1160

Table 31 – Class: CIM_BaseMetricValue – Current Data

Properties	Requirement	Notes
Timestamp	Mandatory	None
Volatile	Mandatory	Matches TRUE

1161 **10.13 CIM_BaseMetricValue — Interval Metrics**

1162 CIM_BaseMetricValue reports a metric defined using CIM_BaseMetricDefinition. Table 32 describes the 1163 requirements for using CIM_BaseMetricValue to report the metric for interval metrics. These constraints

are in addition to those specified in 10.11.

1165

Table 32 – Class: CIM_BaseMetricValue – Interval Metrics

Properties	Requirement	Notes
Duration	Mandatory	None
Timestamp	Mandatory	None

1166 **10.14 CIM_BaseMetricValue — Startup Interval Metrics**

1167 CIM_BaseMetricValue reports a metric defined using CIM_BaseMetricDefinition. Table 33 describes the 1168 requirements for using CIM_BaseMetricValue to report the metric for startup interval metrics. These

1169 constraints are in addition to those specified in 10.11.

1170

Table 33 – Class: CIM_BaseMetricValue – Startup Interval Metrics

Properties	Requirement	Notes
Duration	Mandatory	None
Timestamp	Mandatory	None

1171 **10.15 CIM_BaseMetricValue — Summation Metric**

1172 CIM_BaseMetricValue reports a metric defined using CIM_BaseMetricDefinition. Table 34 describes the 1173 requirements for using CIM_BaseMetricValue to report the metric for a Summation Metric. These

1174 constraints are in addition to those specified in 10.11.

1175

Table 34 – Class: CIM_BaseMetricValue – Summation Metric

Properties	Requirement	Notes
Timestamp	Mandatory	None

1176 **10.16 CIM_BaseMetricValue — Long-Term Monitoring**

1177 CIM_BaseMetricValue reports a metric defined using CIM_BaseMetricDefinition. Table 35 describes the

1178 requirements for using CIM_BaseMetricValue to report a metric for long-term monitoring. These

1179 constraints are in addition to those specified in 10.11.

1180

Table 35 – Class: CIM_BaseMetricValue – Long-Term Monitoring

Properties	Requirement	Notes
Volatile	Mandatory	Matches FALSE

1181 **10.17 CIM_ConcreteDependency (Definition)**

- 1182 Table 36 details the requirements for instances of CIM_ConcreteDependency.
- 1183

Table 36 – Class: CIM_ConcreteDependency (Definition)

Elements	Requirement	Notes
Antecedent	Mandatory	Key: This property shall be a reference to CIM_BaseMetricDefinition.
		Cardinality 01
Dependent	Mandatory	Key: This property shall be a reference to CIM_AggregationMetricDefinition.
		Cardinality 01

1184 **10.18 CIM_ConcreteDependency (Value)**

1185 Table 37 details the requirements for instances of CIM_ConcreteDependency.

1186

Table 37 – Class: CIM_ConcreteDependency (Value)

Elements	Requirement	Notes
Antecedent	Mandatory	Key: This property shall be a reference to CIM_BaseMetricValue.
		Cardinality 01
Dependent	Mandatory	Key: This property shall be a reference to CIM_AggregationMetricValue.
		Cardinality 01

1187 **10.19 CIM_ElementCapabilities**

1188 CIM_ElementCapabilities associates an instance of CIM_MetricServiceCapabilities with the Central 1189 Instance. Table 38 details the requirements for instances of CIM_ElementCapabilities.

1190

Table 38 – Class: CIM_ElementCapabilities

Elements	Requirement	Notes
ManagedElement	Mandatory	Key: This property shall be a reference to the Central Instance.
		Cardinality 1
Capabilities	Mandatory	Key: This property shall be a reference to an instance of CIM_MetricServiceCapabilities.
		Cardinality 1

1191 **10.20 CIM_HostedService**

- 1192 Table 39 details the requirements for instances of CIM_HostedService.
- 1193

Table 39 – Class: CIM_HostedService

Elements	Requirement	Notes
Antecedent	Mandatory	Key: This property shall be a reference to the Scoping Instance.
		Cardinality 1
Dependent	Mandatory	Key: This property shall be a reference to the Central Instance.
		Cardinality 1*

1194 **10.21 CIM_MetricDefForME**

1195 CIM_MetricForME relates a metric to the managed element for which it was measured. Table 40 details

1196 the requirements for instances of CIM_MetricDefForME.

1197

Table 40 – Class: CIM_MetricDefForME

Properties	Requirement	Notes
Antecedent	Mandatory	Cardinality 1*
Dependent	Mandatory	Cardinality *
MetricCollectionEnabled	Mandatory	None

1198 **10.22 CIM_MetricForME**

1199 CIM_MetricForME relates a metric to the managed element for which it was measured. Table 41 details 1200 the requirements for instances of CIM_MetricForME.

1201

Table 41 – Class: CIM_MetricForME

Properties	Requirement	Notes
Antecedent	Mandatory	Cardinality 1*
Dependent	Mandatory	Cardinality *

1202 10.23 CIM_MetricInstance

1203 CIM_MetricInstance relates a CIM_BaseMetricValue to the CIM_BaseMetricDefinition that defines it. 1204 Table 42 details the requirements for instances of CIM_MetricInstance.

1205

Table 42 – Class: CIM_MetricInstance

Properties	Requirement	Notes
Antecedent	Mandatory	See 7.1.2.
		Cardinality 1
Dependent	Mandatory	See 7.1.2.
		Cardinality *

1206 **10.24 CIM_MetricService**

1207 Table 43 details the requirements for instances of CIM_MetricService.

1208

Table 43 – Class: CIM_MetricService

Elements	Requirement	Notes
SystemCreationClassName	Mandatory	Кеу
CreationClassName	Mandatory	Кеу
SystemName	Mandatory	Кеу
Name	Mandatory	Кеу
ElementName	Mandatory	Pattern ".*"
ShowMetrics()	Conditional	See 8.1.
ShowMetricsByClass()	Conditional	See 8.2.
ControlMetrics()	Conditional	See 8.3.
ControlMetricsByClass()	Conditional	See 8.4.
GetMetricValues()	Conditional	See 8.5.

1209 **10.25 CIM_MetricServiceCapabilities**

1210 CIM_MetricServiceCapabilities indicates support for managing the state of the service as well as the

accounts with which the service is associated. Table 44 details the requirements for instances of

1212 CIM_MetricServiceCapabilities.

1213

Table 44 – Class: CIM_MetricServiceCapabilities

Elements	Requirement	Notes
InstanceID	Mandatory	None
ElementName	Mandatory	Pattern ".*"
SupportedMethods	Mandatory	None
ControllableMetrics	Mandatory	None
MetricControlTypes	Mandatory	None
ControllableManagedElements	Mandatory	None
ManagedElementControlTypes	Mandatory	None

1214 **10.26 CIM_RegisteredProfile**

1215 CIM_RegisteredProfile identifies the Base Metrics Profile. The CIM_RegisteredProfile class is defined by

the <u>Profile Registration Profile</u>. With the exception of the mandatory values specified for the properties in Table 45, the behavior of the CIM_RegisteredProfile instance is in accordance with the constraints

1218 specified in the *Profile Registration Profile*.

1219

Table 45 – Class: CIM_RegisteredProfile

Properties	Requirement	Notes	
RegisteredNameMandatoryThis property shall have a value of "Base Metrics".		This property shall have a value of "Base Metrics".	
RegisteredVersion	Mandatory	This property shall have a value of "1.0.1".	
RegisteredOrganization	Mandatory	This property shall have a value of 2 (DMTF).	

1220 **10.27 CIM_ServiceAffectsElement**

1221 CIM_ServiceAffectsElement is used to associate an instance of CIM_MetricService with an instance of 1222 CIM_BaseMetricDefinition or CIM_AggregationMetricDefinition that represents a metric that could be

1223 controlled using the service. Table 46 contains the requirements for elements of this class.

1224

Table 46 – Class: CIM_ServiceAffectsElement

Elements	Requirement	Notes	
AffectedElement	Mandatory	Key : This property shall reference the instance of CIM_BaseMetricDefinition or CIM_AggregationMetricDefinition.	
		Cardinality 1*	
AffectingElement	Mandatory	Key : This property shall reference the instance of CIM_MetricService.	
		Cardinality 1	
ElementAffects	Mandatory	Matches 5 (Manages)	

1226 1227 1228 1229 1230

ANNEX A (Informative)

Change Log

Version	Date	Description			
1.0.0	2009-06-16	DMTF Standard			
1.0.1	2009-12-11	DMTF Standard, with the following changes:			
		 Corrected inconsistencies based on the published profiles incorporating metric definitions and DSP0004 programmatic unit definitions. 			

1232 1233	ANNEX B (Informative)		
1234			
1235	Guide for Common Metrics		

This annex provides an informative list of the combined mandatory properties for instances of
CIM_BaseMetricDefinition, CIM_AggregationMetricDefinition, CIM_BaseMetricValue, and
CIM_AggregationMetricValue if used to represent common metrics. Each of the data cells of the tables
lists mandatory properties and their value formulations for a specific type of metric. Each table
corresponds to a different type of metrics grouped by value formulation. The rows represent the different
type of metrics based on the time scope that metric describes. The columns describe the different type of
metrics based on the metric collection access type used.

- 1243 In order to determine the mandatory set of properties, match the type of metric to one of the data cells 1244 based on the metric's value formulation, time scope, and collection access type.
- 1245 The following conventions are used in the table:
- BMD the properties that follow are required on the instance of CIM_BaseMetricDefinition
- BMV the properties that follow are required on the instance of CIM_BaseMetricValue
- AMD the propertiest that follow are required on the instance of CIM_AggregationMetricDefinition
- AMV the properties that follow are required on the instance of CIM_AggregationMetricValue
- A property name without a value specified is required, and the value is not fixed.
- A property name followed by a value assignment is required with the specified value fixed.
- NOTE: If there is a mismatch between the mandatory set of properties and/or the properties' value formulation
 indicated by the tables in this annex and the requirements detailed in clauses 7 and 10, the requirements
 mandated in clauses 7 and 10 take precedence.

1256 B.1 Simple Metric

1257 Table B.1 describes the mandatory properties for simple metric as described in 6.3.1 according to the 1258 appropriate metric access type and time scope.

Table B.1 – Simple Metric

			Current Data –		
	Current Data	Current Data – Online Monitoring	Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	BMD	BMD	BMD	BMD	BMD
	ChangeType	ChangeType	ChangeType	ChangeType	ChangeType
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType Id	GatheringType = 3 (Periodic) or 2 (OnChange)	GatheringType = 4 (OnRequest)	GatheringType Id	GatheringType Id
rics	IsContinuous = TRUE	Id IsContinuous =	ld IsContinuous = TRUE	IsContinuous = TRUE	IsContinuous = TRUE
us Met	TimeScope = 2 (Point) ProgrammaticUnits	TRUE TimeScope = 2	TimeScope = 2 (Point)	TimeScope = 2 (Point) ProgrammaticUnits	TimeScope = 2 (Point) ProgrammaticUnits
Instantaneous Metrics	Name	(Point) ProgrammaticUnits	ProgrammaticUnits Name	Name	Name
ısta		Name			
-	BMV	BMV	BMV	BMV	BMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration		
	Timestamp	Timestamp	Timestamp		
	BMD	BMD	BMD	BMD	BMD
	ChangeType	ChangeType	ChangeType	ChangeType	ChangeType
	DataType ElementName	DataType	DataType	DataType	DataType
	GatheringType	ElementName	ElementName	ElementName	ElementName
	Id	GatheringType = 3 (Periodic) or 2	GatheringType = 4 (OnRequest)	GatheringType	GatheringType
	TimeScope = 3	(OnChange)	Id	ld	ld
s	(Interval)	ld	TimeScope = 3	TimeScope = 3 (Interval)	TimeScope = 3 (Interval)
etri	ProgrammaticUnits	TimeScope = 3	(Interval)	ProgrammaticUnits	ProgrammaticUnits
M	Name	(Interval) ProgrammaticUnits	ProgrammaticUnits	Name	Name
Interval Metrics		Name	Name		
In	BMV	BMV	BMV	BMV	BMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	BMD	BMD	BMD	BMD	BMD
	ChangeType	ChangeType	ChangeType	ChangeType	ChangeType
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
Startup Metrics	GatheringType Id TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	GatheringType = 3 (Periodic) or 2 (OnChange) Id TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	GatheringType = 4 (OnRequest) Id TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	GatheringType Id TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	GatheringType Id TimeScope = 4 (StartupInterval) ProgrammaticUnits Name
Š	BMV	BMV	BMV	BMV	BMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp

1260 B.2 Summation Metric

1261 Table B.2 describes the mandatory properties for summation metric as described in 6.3.2 according to the 1262 appropriate metric access type and time scope.

Table B.2 – Summation Metric

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	BMD	BMD	BMD	BMD	BMD
	ChangeType = 3 (Counter)				
	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)
ics	ElementName	ElementName	ElementName	ElementName	ElementName
letr	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
N Sr	Id	(Periodic) or 2 (OnChange)	(OnRequest)	Id	Id
aneot	IsContinuous = TRUE	ld	Id IsContinuous =	IsContinuous = TRUE	IsContinuous = TRUE
Instantaneous Metrics	TimeScope = 2 (Point) ProgrammaticUnits	IsContinuous = TRUE TimeScope = 2	TRUE TimeScope = 2 (Point)	TimeScope = 2 (Point) ProgrammaticUnits	TimeScope = 2 (Point) ProgrammaticUnits
	Name	(Point) ProgrammaticUnits	ProgrammaticUnits Name	Name	Name
		Name			
	BMV	BMV	BMV	BMV	BMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Timestamp	Timestamp	Timestamp		

¹²⁶³

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	BMD	BMD	BMD	BMD	BMD
	ChangeType = 3 (Counter)				
	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)
cs	ElementName	ElementName	ElementName	ElementName	ElementName
Interval Metrics	GatheringType Id	GatheringType = 3 (Periodic) or 2 (OnChange)	GatheringType = 4 (OnRequest)	GatheringType Id	GatheringType Id
Interva	TimeScope = 3 (Interval) ProgrammaticUnits	Id TimeScope = 3	ld TimeScope = 3 (Interval)	TimeScope = 3 (Interval) ProgrammaticUnits	TimeScope = 3 (Interval) ProgrammaticUnits
	Name	(Interval) ProgrammaticUnits Name	ProgrammaticUnits Name	Name	Name
	BMV	BMV	BMV	BMV	BMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
	BMD	BMD	BMD	BMD	BMD
	ChangeType = 3 (Counter)				
Startup Metrics	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)
artu	ElementName	ElementName	ElementName	ElementName	ElementName
St	GatheringType Id	GatheringType = 3 (Periodic) or 2 (OnChange)	GatheringType = 4 (OnRequest)	GatheringType Id	GatheringType Id
	TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	Id TimeScope = 4 (StartupInterval)	ld TimeScope = 4 (StartupInterval) ProgrammaticUnits	TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	TimeScope = 4 (StartupInterval) ProgrammaticUnits Name
		ProgrammaticUnits	Name		

Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
BMV	BMV	BMV	BMV	BMV
MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
Timestamp	Timestamp	Timestamp	Timestamp	Timestamp

1264 **B.3 Aggregation Metric**

Table B.3 describes the mandatory properties for aggregation metric as described in section 6.3.3according to the appropriate metric access type and time scope.

1267

Table B.3 – Aggregation Metric

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType Id IsContinuous =	GatheringType = 3 (Periodic) or 2 (OnChange)	GatheringType = 4 (OnRequest) Id	GatheringType Id IsContinuous =	GatheringType Id IsContinuous =
s Metrics	TRUE TimeScope = 2 (Point) ProgrammaticUnits Name	Id IsContinuous = TRUE TimeScope = 2 (Point)	IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits	TRUE TimeScope = 2 (Point) ProgrammaticUnits Name	TRUE TimeScope = 2 (Point) ProgrammaticUnits Name
Instantaneous Metrics	SimpleFunction	ProgrammaticUnits Name SimpleFunction	Name SimpleFunction	SimpleFunction	SimpleFunction
lns	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration Timestamp	Duration Timestamp	Duration Timestamp	AggregationTime- Stamp	AggregationTime- Stamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationDuration	AggregationDuration
	AggregationDuration	AggregationDuration	AggregationDuration		

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType Id	GatheringType = 3 (Periodic) or 2	GatheringType = 4 (OnRequest)	GatheringType Id	GatheringType Id
etrics	TimeScope = 3 (Interval) ProgrammaticUnits Name SimpleFunction	(OnChange) Id TimeScope = 3 (Interval) ProgrammaticUnits	Id TimeScope = 3 (Interval) ProgrammaticUnits Name	TimeScope = 3 (Interval) ProgrammaticUnits Name	TimeScope = 3 (Interval) ProgrammaticUnits Name
Interval Metrics		Name SimpleFunction	SimpleFunction	SimpleFunction	SimpleFunction
Inte	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
cs	ElementName	ElementName	ElementName	ElementName	ElementName
letrics	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	Id	(Periodic) or 2 (OnChange)	(OnRequest)	ld	ld
Startup N	TimeScope = 4 (StartupInterval) ProgrammaticUnits	Id TimeScope = 4	ld TimeScope = 4 (StartupInterval)	TimeScope = 4 (StartupInterval) ProgrammaticUnits	TimeScope = 4 (StartupInterval) ProgrammaticUnits
	Name	(StartupInterval) ProgrammaticUnits	ProgrammaticUnits	Name	Name
	SimpleFunction	Name SimpleFunction	Name SimpleFunction	SimpleFunction	SimpleFunction

Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
AMV	AMV	AMV	AMV	AMV
MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
Duration	Duration	Duration	Duration	Duration
Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration

1268 B.4 Aggregation Metric — Low Watermark

1269Table B.4 describes the mandatory properties for low watermark as a type of an aggregation metric as1270described in section 6.3.3.1 according to the appropriate metric access type and time scope.

1271

Table B.4 – Aggregation Metric – Low Watermark

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
s	ElementName	ElementName	ElementName	ElementName	ElementName
Metrics	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	ld	(Periodic) or 2 (OnChange) Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name		ld	ld
Instantaneous	IsContinuous = TRUE		Id IsContinuous =	IsContinuous = TRUE	IsContinuous = TRUE
tantai	TimeScope = 2 (Point)		TDUE	TimeScope = 2 (Point)	TimeScope = 2 (Point)
lns	ProgrammaticUnits		ProgrammaticUnits ProgrammaticUnits Name SimpleFunction = 2	ProgrammaticUnits	ProgrammaticUnits
	Name			Name	Name
	SimpleFunction = 2 (Minimum)			SimpleFunction = 2 (Minimum)	SimpleFunction = 2 (Minimum)
		SimpleFunction = 2 (Minimum)	(Minimum)		

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	AggregationTime-	AggregationTime-
	Timestamp	Timestamp	Timestamp	Stamp	Stamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationDuration	AggregationDuration
	AggregationDuration	AggregationDuration	AggregationDuration		
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	Id	(Periodic) or 2 (OnChange)	(OnRequest)	ld	Id
	TimeScope = 3	ld	ld Time Coone - 2	TimeScope = 3	TimeScope = 3
	(Interval) ProgrammaticUnits	TimeScope = 3	TimeScope = 3 (Interval)	(Interval) ProgrammaticUnits	(Interval) ProgrammaticUnits
cs	Name	(Interval)	ProgrammaticUnits	Name	Name
etri	SimpleFunction = 2	ProgrammaticUnits	Name	SimpleFunction = 2	SimpleFunction = 2
N N	(Minimum)	Name	SimpleFunction = 2	(Minimum)	(Minimum)
Interval Metrics		SimpleFunction = 2 (Minimum)	(Minimum)		
Int	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	ld	(Periodic) or 2 (OnChange)	(OnRequest)	Id	Id
	TimeScope = 4 (StartupInterval) ProgrammaticUnits	ld TimeScope = 4	ld TimeScope = 4 (StartupInterval)	TimeScope = 4 (StartupInterval) ProgrammaticUnits	TimeScope = 4 (StartupInterval) ProgrammaticUnits
ics	Name	(StartupInterval) ProgrammaticUnits	ProgrammaticUnits	Name	Name
Startup Metrics	SimpleFunction = 2 (Minimum)	Name SimpleFunction = 2 (Minimum)	Name SimpleFunction = 2 (Minimum)	SimpleFunction = 2 (Minimum)	SimpleFunction = 2 (Minimum)
Ś	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration

1272 B.5 Aggregation Metric — High Watermark

1273 Table B.5 describes the mandatory properties for high watermark as a type of an aggregation metric as 1274 described in section 6.3.3.1 according to the appropriate metric access type and time scope.

1275	
------	--

Table B.5 – Aggregation Metric – High Watermark

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	Id	(Periodic) or 2 (OnChange)	(OnRequest)	ld	Id
	IsContinuous = TRUE	ld	ld IsContinuous =	IsContinuous = TRUE	IsContinuous = TRUE
letrics	TimeScope = 2 (Point) ProgrammaticUnits	IsContinuous = TRUE TimeScope = 2	TRUE TimeScope = 2 (Point)	TimeScope = 2 (Point) ProgrammaticUnits	TimeScope = 2 (Point) ProgrammaticUnits
<u>s</u>	Name	(Point) ProgrammaticUnits	ProgrammaticUnits	Name	Name
Instantaneous Metrics	SimpleFunction = 3 (Maximum)	Name SimpleFunction = 3 (Maximum)	Name SimpleFunction = 3 (Maximum)	SimpleFunction = 3 (Maximum)	SimpleFunction = 3 (Maximum)
Ins	AMV	ΑΜΥ	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	AggregationTime-	AggregationTime-
	Timestamp	Timestamp	Timestamp	Stamp	Stamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationDuration	AggregationDuration
	AggregationDuration	AggregationDuration	AggregationDuration		

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType Id	GatheringType = 3 (Periodic) or 2	GatheringType = 4 (OnRequest)	GatheringType Id	GatheringType Id
	TimeScope = 3	(OnChange)	Id	TimeScope = 3	TimeScope = 3
	(Interval) ProgrammaticUnits	ld TimeScope = 3	TimeScope = 3 (Interval)	(Interval) ProgrammaticUnits	(Interval) ProgrammaticUnits
cs	Name	(Interval)	ProgrammaticUnits	Name	Name
etri	SimpleFunction = 3	ProgrammaticUnits	Name	SimpleFunction = 3	SimpleFunction = 3
al	(Maximum)	Name	SimpleFunction = 3	(Maximum)	(Maximum)
Interval Metrics		SimpleFunction = 3 (Maximum)	(Maximum)		
-	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
cs	ElementName	ElementName	ElementName	ElementName	ElementName
itric	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
Ň	ld	(Periodic) or 2 (OnChange)	(OnRequest)	Id	ld
Startup Metri	TimeScope = 4 (StartupInterval) ProgrammaticUnits	Id TimeScope = 4	ld TimeScope = 4 (StartupInterval)	TimeScope = 4 (StartupInterval) ProgrammaticUnits	TimeScope = 4 (StartupInterval) ProgrammaticUnits
	Name	(StartupInterval)	ProgrammaticUnits	Name	Name
	SimpleFunction = 3 (Maximum)	ProgrammaticUnits Name SimpleFunction = 3 (Maximum)	Name SimpleFunction = 3 (Maximum)	SimpleFunction = 3 (Maximum)	SimpleFunction = 3 (Maximum)

Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
AMV	AMV	AMV	AMV	AMV
MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
Duration	Duration	Duration	Duration	Duration
Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration

1278 Bibliography

1279 DMTF DSP1073, Capacity Metrics Profile 1.0